

Recover Windows 7 password, restore Win 7 Pro, Ultimate password.

There are many ways to recover your Windows 7 computer password, ranging from easy to difficult. However, not every case can be solved with a single method. Therefore, in this article, we will guide you through another way to recover your Windows 7 Pro password.

There are many ways to recover your Windows 7 password , and how many of them do you know? This is because not all methods work for all cases of forgotten Windows 7 passwords. The **more methods** you know , the higher your chances of recovering your forgotten password.




In this article, TipsMake will guide you on using **Command Prompt** along with **the Registry** , two very useful components with many yet-to-be-explored features, to recover your Windows 7 password. Furthermore, this method can be applied to many different situations when you forget your password and across various operating systems. Therefore, readers should carefully review the instructions below before attempting this.

Recover Windows 7 password, restore Win 7 password

Step 1: To recover your Windows 7 password, you need a DVD containing the Windows 7 installation files or at least a USB drive containing the installation files. If you don't know how to create one, you can refer to the Windows 7 installation guide and follow the instructions.


Step 2: You proceed with the initial steps of installing Windows 7 as usual by selecting Next.




Step 3: But here, instead of selecting "**Install now** ," choose "**Repair your computer** ."




Step 4: At this point, the system will give you 5 options to repair the computer; we choose **Command Prompt** .




Step 5: When the Command Prompt screen appears, type the command regedit to open the Registry Editor .




Step 6: Next, click on **HKEY_LOCAL_MACHINE** and then select **File > Load Hive** .




Step 7: In the Load Hive section, open the file using the following command:
D:Windows\System32configSYSTEM and click **Open** .




Step 8: The system will now ask you to enter a new folder. You can name it anything, but remember to keep it short. Here, TipsMake entered **111**.




Step 9: In section 111, open the **Setup** folder.




Step 10: Click on **Cmdline** and change the value to **cmd.exe** , then **click OK** .




Below, click on **SetupType** and change the value to **2** .




Step 11: Finally, click on **item 111** again , then select **File > Unload Hive** .




The system will ask if you are sure you want to exit this section; select **Yes** to close the Registry Editor.



Step 12: Then exit completely and restart your computer. The Command Prompt window will automatically appear on the screen. Enter **the command** ``net user`` to check your account balance.



Step 13: Next, simply check the machine's account and use the ``net use` syntax`. To proceed with setting a password for the account.



```
Administrator: cmd.exe
Microsoft Windows [Version 10.0.15063]
(c) 2017 Microsoft Corporation. All rights reserved.
C:\WINDOWS\system32>net user

User accounts for \\

Administrator          DefaultAccount         Guest
taini
The command completed with one or more errors.
C:\WINDOWS\system32>net user taini 123456_
```

After completing this step, close Command Prompt and you will immediately be able to access Windows 7 with the password you just set.

So, we've completed the process of recovering your Windows 7 password. This method is a bit complicated and lengthy, but it's highly effective and applicable to many cases of forgotten computer passwords. If you've exhausted all other methods to recover your Windows 7 password, this is one option you should remember in case you forget your computer password. Furthermore, this method works for both Windows 8 and Windows 10.

To avoid having to recover your computer password later, when setting your computer password, you should save it to a password reminder app or on your phone. Also, remember to choose a password that is easy for you to remember.

You should also make it a habit to change your computer password. This is a better way to protect your computer and avoid forgetting it like before. It only takes a little time to successfully change your computer password .

You finished reading the article "**Recover Windows 7 password, restore Win 7 Pro, Ultimate password.**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.