

Create a Windows 7 installation DVD with built-in SP1

Although Service Pack 1 version for Windows 7 is not complete, many readers still want to integrate the SP1 version for Windows 7.

Although the Service Pack 1 version for Windows 7 is not yet complete, many readers still want to integrate the SP1 test for Windows 7.

By tapping the **RT Seven Lite** tool, you can create an ISO file that installs Windows 7 SP1. Readers can also apply the method in the article to integrate the completed SP1 version when it is officially released by Microsoft.

Step 1: First, users access here to download **RT Seven Lite** tool. After downloading, please install and start this software. It is recommended to select **RT Seven Lite v2.0** or higher version.



The working interface of RT Seven Lite.


Step 2: Under the **Home** tab, click the **Browse** button to browse to the **ISO** file of Windows 7 installation or the installation directory of this operating system. If you choose the ISO option, you will also need to specify a location to extract the ISO file, the article will work with the popular option of using the original ISO file of Windows 7.

Step 3: You will see the data extraction process done with time may take a while. When done, you will be prompted to select your version of Windows 7. Select the appropriate version, please check before choosing **Slipstream Service Pack** before clicking **OK** to continue.



Select the appropriate version of Windows 7.

Step 4: At this time the **Slipstream RT Service Pack** dialog box will open. Just enter the **SP1** file for Windows 7 by clicking on the left Browse button and navigate to the SP1 file path before clicking the Start button to start the integration process.




Integrate the SP1 file to create the DVD.

Step 5: Wait a few minutes until you see the **Proceed** button appear, **click** this button to start downloading images and other things. After doing so, please switch to the **Task** tab to continue the work.

Step 6: Under the **Task** tab, go to the **ISO Bootable option** to pre-check it, then switch to the **ISO-Bootable** tab.

Step 7: Here select the **Create Image** option in the Mode drop-down list. If you want to directly burn the files to a DVD, select the **Direct Burn** option in the Mode drop-down list. In this tutorial, the article will select the **Create Image** option.



Step 8: Now click on the **Make ISO** button and choose a location to save your ISO file. Windows 7 SP1 ISO image file is ready for you to proceed to burn a new special Windows 7 installation disc.

You finished reading the article "**Create a Windows 7 installation DVD with built-in SP1**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.