

Disable all Live Tile at the same time on Windows 10 Start Menu

Live Tile is a very useful feature on Windows 8 / 8.1 and Windows 10. However, the limitation of this feature is to take up Internet bandwidth to update the preview and notifications. Sometimes in some cases Live Tile also makes users feel annoying.

Live Tile is a very useful feature on Windows 8 / 8.1 and Windows 10. However, the limitation of this feature is to take up Internet bandwidth to update the preview and notifications. Sometimes in some cases Live Tile also makes users feel annoying.

By default, to disable Live Tile options on Windows 10 Start Menu, just right-click on the application and select **More => Turn live tile off** to finish.

However, on Windows 10 Start Menu, there are many Live Tile settings, so it will take a lot of time to disable Live Tile on each application. So to save time, you can disable all Live Tile on Windows 10 Start Menu at the same time.


To disable all Live Tile on Windows 10 Start Menu at the same time, please refer to the following article of Network Administrator.



1. Disable all Live Tile at the same time on Windows 10 Start Menu


To disable all Live Tile at the same time on Windows 10 Start Menu, follow the steps below:

1. Press the **Windows + R** key combination to open the Run command window.



At the Run command window, enter **gpedit.msc** there and press **Enter** to open the Group Policy Editor.


2. Now on the screen that appears the Group Policy Editor window.




3. Here you navigate by key:

Local Computer Policy => User Configuration => Administrative Templates => Start Menu and Taskbar => Notifications

4. Next, find and double-click the option **Turn off tile notifications** .




5. Now on the screen the Turn off tile notifications dialog box appears, here you click the **Enable** option then click **OK** , close the Turn off tile notifications window again.




6. Finally log off your Windows 10 computer and log back in to check for changes.

Before:



After:




2. On Windows 10 versions, there is no Group Policy Editor

With versions of Windows 10 without the Group Policy Editor, users can disable all Live Tile with the Registry.

1. Open Registry Editor.
2. In the Registry Editor window, navigate to the key:


HKEY_CURRENT_USERSOFTWAREPoliciesMicrosoftWindowsCurrentVersionPushNotifications



Note:

If you can't find a key, you can create those keys.

3. In the right pane, you create a new 320-bit DWORD value, name this value **NoTileApplicationNotification** and set the value in the Value data frame to **1** to disable all Live Tiles on the Windows 10 Start Menu. .



4. Finally log off your Windows 10 computer and log back in to check for changes.

If you want to restore everything by default, you only need to delete the NoTileApplicationNotification value that you created, then proceed to log off and then log in to Windows 10 again to check.

Refer to some of the following articles of Network Administrator:

1. Instructions to mount the hard drive into a folder on Windows 10
1. Steps to disable or completely remove the Onedrive application on Windows 10

1. How to combine multiple hard drives into a Volume on Windows 10

Good luck!

You finished reading the article "**Disable all Live Tile at the same time on Windows 10 Start Menu**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.

© 2019 TipsMake.com