

Fix ClipChamp not working error on Windows 11


While using ClipChamp, you may also encounter some errors such as not being able to use ClipChamp when clicking. Below are some instructions on how to fix ClipChamp not working on Windows 11.

ClipChamp is a built-in application on Windows 11 for you to view and edit videos. While using ClipChamp, you may also encounter some errors such as not being able to install ClipChamp or not being able to use ClipChamp when clicking. Below are some instructions on how to fix ClipChamp not working on Windows 11.

Fix ClipChamp not working via Settings

Step 1:


You type **ClipChamp** in the search bar , then **click on App Settings** as shown below.



Step 2:

Display the ClipChamp application installation interface, **click the Repair button** to repair the application that is having problems.

If ClipChamp still doesn't work, you can reset the app, which will erase all data and return it to its original default look. Tap Reset to reinstall the app.




Fix ClipChamp not working with SFC Scannow command

The SFC Scannow command automatically detects corrupted, damaged ClipChamp files and finds the correct file version.

Step 1:

You need to **open Terminal as administrator** on your computer.



Step 2:

In this interface, you **enter the command sfc /scannow**. Then the corrupted files will be displayed and notified on the screen. You follow the displayed instructions and Windows will automatically reload all corrupted files.

```
Administrator: Windows Powe x + v - □ ×
Windows PowerShell
Copyright (C) Microsoft Corporation. All rights reserved.

Install the latest PowerShell for new features and improvements! https://aka.ms/PSWindows

PS C:\Users\Dell> sfc /scannow
```

Free up computer RAM

ClipChamp requires a lot of RAM and CPU resources to run. In some cases, ClipChamp will not run or will shut down due to lack of space. This can happen if you are using large or long videos and running other applications at the same time.

Try closing inactive programs, like Chrome or other heavy programs, to free up your computer's memory.

You can also use Task Manager to close background programs that you are not using.

1. 8 Task Manager tips that Windows users should know

Turn off anti-virus or anti-scam software on Windows

If you are using third-party antivirus software, temporarily disable it and try running ClipChamp again. Alternatively, you can allow ClipChamp through your firewall.


Step 1:

Open **Settings** and select **Privacy and security** , then click **Windows Security > Firewall & network protection** .




Step 2:

Switch to the new interface, the user selects **Allow an app through firewall** as shown.




Step 3:

Click **Change settings** again to change the settings.



In the list below , **find Microsoft ClipChamp** and **select both Public and Private options** . Finally, click OK to save.



You finished reading the article "**Fix ClipChamp not working error on Windows 11**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.

