

Fixing the 'No Internet, Secure' error on Windows 10, resolving network access issues.


Windows 10 is an operating system with a beautiful interface and many excellent features. Users of this operating system always receive daily updates with bug fixes and new features. However, Windows 10 still faces an error that prevents users from connecting to the internet: 'No Internet, Secure'. So, how to fix the 'No Internet, Secure' error on Windows 10 and resolve the internet connection issue? Let's find out with TipsMake in the article below.

Whether you're using a Wi-Fi or wired network, you might encounter the "No Internet Secure" error. This usually stems from incorrect IP address settings. Therefore, to fix the "No Internet Secure" error on Windows 10 and resolve the issue of your computer not being able to connect to the network, you can follow the two methods below.


Fixing the "No Internet, Secure" error on Windows 10

Method 1. Run Troubleshooting


Step 1: Search for and open **the Control Panel** from the Start Menu. In the Control Panel window, set **the View by** option to **Large icons** so you can more easily find the **Troubleshooting** section.



Step 2: In the Troubleshooting window, click on **Network and Internet** .




Step 3: Here you will see a list of debugging options. Click on **Network Adapter** and follow the system's instructions to automatically fix the "No Internet, Secure" error on Windows 10.




Method 2. Manual setup


Step 1: Right-click on your network icon in the Taskbar and select **Open Network and Sharing Center** .




Step 2: In the Network and Sharing Center window, click on the **Connections** information for the network you are using.



Step 3: A small window will appear; click on the **Properties** option at the bottom.



Step 4: Find the **Internet Protocol Version 6 (TCP/IPv6)** option and **uncheck** it, then click **OK** in the windows to complete the changes.



These two methods will help you troubleshoot and fix the "No Internet, Secure" error on Windows 10, quickly resolving issues where your computer cannot connect to the network. If you are unable to use the network due to outdated drivers, you can update them using DriverEasy, such as network drivers and VGA drivers.

After successfully fixing internet issues on Windows 10, you can proceed to create a Wi-Fi hotspot on Windows 10 to share your internet connection with smartphones such as iPhones, Androids, Oppos, etc. Creating a Wi-Fi hotspot on Windows 10 is very simple, and the web browsing speed when accessing via this Wi-Fi signal on your phone is also quite good.

If you encounter the "Ethernet doesn't have a valid IP configuration" error on your computer, preventing you from accessing the internet, please refer to the instructions [here](#) to fix this issue.

Many users frequently experience WiFi connection problems. Why does WiFi fail to connect, and how can it be fixed? Don't think this is a complicated issue, because when designing WiFi, manufacturers always aim for simplicity and ease of use. You'll find our point completely true after reading the following articles and guides.

You finished reading the article "**Fixing the 'No Internet, Secure' error on Windows 10, resolving network access issues.**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips

and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.
