

Fix Windows 8 error when encountering a black screen

Windows 8 is preferred because of its smooth interface and features that catch up with the new trend, but Windows 8 users often encounter a black screen error on startup without understanding why and how to fix it.

Windows 8 is preferred because of its smooth interface and features that catch up with the new trend, but Windows 8 users often encounter a black screen error on startup without understanding why and how to fix it.

Black screen error when booting is not caused by virus but due to the fast *Startup feature* of Windows 8. With activating *Fast Startup feature*, Windows 8 will boot up faster. The principle is that every time you turn off your system, your system does not turn off completely, but the drivers and *kernel* are automatically stored in memory (*the task that people call 'shutdown', or Hybrid Shutdown.*), thereby making the machine start faster.


However, this feature has the disadvantage that often makes some machines using Win 8 black screen error on startup and you often do not understand why and do not know how to fix.

In fact, to **remove the black screen** , simply **turn off Fast Startup** with 5 steps.

Fix Win 8 error when encountering black screen:


Step 1: If you encounter a black screen when booting Windows 8, find a way to disconnect the power to restart. You can use **the power button** to **keep the** device turned off and then on again.

Step 2: After the machine restarts, click **Control Panel** outside the Desktop (*or you can open it in the Start menu*).




Fix Win 8 error when encountering a black screen: After the machine restarts, click Control Panel outside the Desktop screen.

Step 3: In *Control Panel* go to **Power Options**, then go to **Choose what the power buttons link** on the left.




Fix Win 8 error when encountering black screen: In Control Panel go to Power Options, then the word to the link 'Choose what the power buttons do'

Step 4: Click on the **Change settings link that is currently unavailable** .



Fix Win 8 error when meeting black screen: Click on the 'Change settings that are currently unavailable' link

Step 5: Check **Turn on fast startup** (*recommended*) at the bottom and click **Save changes** and restart the computer.



Fix the Win 8 error when encountering the black screen: Check 'Turn on fast startup (recommended)' (arrow) at the bottom and press 'Save changes' (circled in red) and restart the computer.

You finished reading the article "**Fix Windows 8 error when encountering a black screen**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.
