


How to change the display language in Windows 7

This tutorial will show you how to change the display language in Windows 7 to one of 30 languages ?? supported by Microsoft.

If you buy a computer running the English version of Windows 7, however, English is not your native language, this guide will show you how to change the display language in Windows 7 to one of 30 languages ??supported by Microsoft on Win 7.

We will use Windows 7 Ultimate in this tutorial, but you can also apply to all other Windows 7 versions. If you want to install Vietnamese for Windows 7, please see the article [How to switch to Vietnamese interface for Windows 7 with quick, easier and available steps to download Vietnamese file download for Windows 7 without installing through Windows Update](#). The steps below you can use to install other languages ??such as Chinese, Spanish, . for Windows 7.

Install Region and Language in Windows 7




1. To get started, click the **Start** button (Windows Logo) to open the **Start Menu** .
2. When the Start Menu opens, enter " **change display language** " in the Windows search box.
3. The list of search results will appear in the Start Menu, click **Change display language** from the list.

4. The **Region and Language** window will appear. Activate the **Keyboards and Languages** tab.
5. Click the **Install / Uninstall Languages** button

In order for you to use languages other than the default language installed in Windows, you will need to download them from Microsoft, then install the language pack for the language you want to use.

Install additional language packs from Windows Update



Install or uninstall display languages will appear prompting you to install the language to display or uninstall the display language.


Click **Install** to download the language pack.

You will then be prompted to choose the location of the language pack with two options, **Launch Windows Update** or **Browse computer or network**.

Unless you already have a language pack stored on your PC, click **Launch Windows Update** to download the latest language packs directly from Microsoft.

Use the Windows Update Optional Updates to download language packs

Windows Update



Most recent check for updates: Today at 1:21 PM
Updates were installed: 6/7/2011 at 3:00 AM. [View update history](#)
You receive updates: For Windows and other products from Microsoft

When you select the **Launch Windows Update option**, the **Windows Update** window will appear.


Note: Windows Update is used to download updates, security fixes, language packs, drivers and other features directly from Microsoft.

There are two types of updates that are usually available from Windows Update, important updates and must be downloaded immediately and updates are not required.

Language packs that fall into an optional update are not important, so you will need to manually select the language pack you want to use to download from Windows Update.

Click on the **# optional updates link in the available** (# refers to the number of optional updates available for download) in Windows Update.


Choose a language pack to download and install



The **Select updates to install page** will display a list of **Important** and **Optional** updates.

1. Enable **Optional** tab.
2. Select the language you want to use by adding a check mark next to the language pack in the list from the **Windows 7 Language Packs section** .
3. When the language pack has been selected, click **OK** .


Download & Install language pack



You will be returned to the **Windows Update** page where you will click the **Install Updates** button to start downloading the language packs you have selected from the list.

After language packs are downloaded and installed, they will be ready for use.

Select the display language you want to use



When you return to the **Region and Language** dialog box, select the languages you just downloaded from the **Choose a display language** menu.

When you select the language, click **OK** to save the changes.

In order for the new display language to work, you will need to log out of the computer. When you log in again, the display language you selected will work.

See more:

1. How to change the language of Google Chrome?
2. How to change the language on Coc Coc browser

You finished reading the article "**How to change the display language in Windows 7**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.