

# How to change the Taskbar position on Windows 11 to the left, right, top, or bottom.

Windows 11 brings impressive interface changes, especially the Taskbar, which now centers the icons on the screen. However, if you're not used to this, you can easily move it back to the familiar left-hand position like in previous Windows versions. This article will guide you on how to change the Taskbar position on Windows 11 to center or left.

One of the major changes Microsoft introduced in Windows 11 is the position of the taskbar and **Start menu** . Instead of being on the left side of the screen, they are now in the middle. Of course, Windows 11 also gives users the option to move the Taskbar to the left, as in previous versions of Windows. You can easily **change the Taskbar position on Windows 11** with just a few simple steps.



## Instructions on how to change the Taskbar position on Windows 11


### Table of Contents:

1. How to change the Taskbar position on Windows 11 to the left, right, top, or bottom .
2. How to change the Taskbar position to the top of the Windows 11 screen .

*1. How to change the Taskbar position on Windows 11 to the left, right, top, or bottom.*


Here are the steps to move the taskbar on Windows 11 to the center or left side of the screen:

**Step 1:** Click the **Windows icon** on the taskbar and select **Settings**, or press the **Windows + I** shortcut key to open **Settings**.



**Step 2:** Select **Personalization** from the left-hand panel and **Taskbar** from the right-hand panel.

**Step 3:** Next, click on the **Taskbar behaviors** option and expand the **Taskbar alignment** menu. Then, select **Left** to move the Windows 11 Taskbar to the left or left-align the Windows 11 taskbar icons, or select **Center** to move the Windows 11 Taskbar to the center.



## 2. How to move the Windows 11 Taskbar to the top of the screen.

Additionally, you can move the Windows 11 taskbar to the top of the screen by tweaking the Windows Registry, although this method is not recommended.


**Note:** Before proceeding, you should back up your Registry settings so you can restore them to their original state if errors occur.

- **See also:** Backing up and restoring the Registry on Windows <https://thuthuat.taimienphi.vn/sao-luu-va-khoi-phuc-registry-tren-windows-24760n.aspx>

To move the taskbar to the top of the screen in Windows 11, follow these steps:

**Step 1: Press the Windows + R** shortcut key to open the **Run** dialog box .

**Step 2: Type regedit** and press **Enter** to open **the Registry Editor**.




**Step 3: Find the key:**

**HKEY\_CURRENT\_USERSOFTWAREMicrosoftWindowsCurrentVersionExplorerStuckRects3**



**Step 7:** Click **OK** and restart your computer to apply the changes. You will then see the taskbar at the top of the screen.



If you want to move the Taskbar back to the bottom of the screen, simply change the value " **01** " to " **03** " in **HKEY\_CURRENT\_USERSoftwareMicrosoftWindowsCurrentVersionExplorerStuckRects3**.

- A value of **03** means the taskbar is at the bottom of the screen.
- A value of **01** means the taskbar is at the top of the screen.
- A value of **00** moves the taskbar to the left.
- A value of **02** moves the taskbar to the right.

In summary, this article has guided you on how to change the Taskbar position on Windows 11. You can easily move the taskbar on Windows 11 from the center to the left, and from the left to the center of the screen with just a few simple steps.

You finished reading the article "**How to change the Taskbar position on Windows 11 to the left, right, top, or bottom.**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.