

How to delete Adobe Creative Cloud when installing Photoshop

Adobe Creative Cloud is Adobe's cloud storage service that is automatically installed on the system, when you install Photoshop, Illustrator, ...

Few people notice that when installing Adobe products such as Photoshop, Illustrator, . there will be cloud storage service automatically installed on the system is Adobe Creative Cloud. This application will appear on the File Explorer navigation pane, and automatically run on the computer system tray.

Although Adobe adds a cloud storage solution that comes with its applications, we don't really need this application. When on the computer you have installed Google Driver, Dropbox, the addition of Adobe Creative Cloud is not necessary. So how to delete Adobe Creative Cloud application when installing Photoshop?

1. 8 tips for Adobe Illustrator help you design faster
2. 45 smart Photoshop tips you need to know (Part 1)
3. 10 common problems in Photoshop and basic remedies


Instructions to delete Adobe Creative Cloud on Windows

Step 1:

To delete the Adobe Creative Cloud application, you first need to download the Adobe Creative Cloud uninstaller application from Adobe according to the link below.


1. Download Creative Cloud Uninstaller tool

The tool will be in the zip end so after downloading, please unzip to use.



Step 2:


Adobe applications you need to turn off completely on the system. Then go to the extracted Creative Cloud Uninstaller tool folder, then click on the installation file.



Step 3:


A message on the computer will appear on the computer that has applications using the Adobe Creative Cloud application, and the deletion of the application will affect those applications. So Photoshop or Illustrator will not be able to save Adobe's Creative Cloud file after it has been removed.

Click **the Uninstall button** to agree to delete the Creative Cloud application. When this process is complete, the user will receive a notification.



Step 4:


Next, we will need to completely delete the Adobe Creative Cloud application from File Explorer, in addition to deleting them in the system tray. Press the **Windows + R** combination to open the Run window and then enter **the regedit keyword** to access the Windows Registry.




Step 5:

Switch to the new interface, visit the link below.

1. HKEY_CURRENT_USERSOFTWAREMicrosoftWindowsCurrentVersionExplorerDesktopNameSpace




Then find the key **{0E270DAA-1BE6-48F2-AC49-960EE002A5DE}** and right-click and **select Delete** to delete this key.



Open File Explorer and you will see no more Creative Cloud on the navigation pane. If the user reinstalls the Creative Cloud application, the corresponding key for the application will automatically be created.

How to edit on Registry Editor can also apply to users who want to use Adobe Creative Cloud, but do not want to appear on File Explorer. You do not need to uninstall the application, just follow the steps in the Windows Registry.



Thus, with Creative Cloud Uninstaller tool from Adobe you can delete the Adobe Creative Cloud cloud storage application. If you want to use the service but do not need to display it on File Explorer, you need to delete the key in the Windows Registry.

See more:

1. Simple puzzle operation in Photoshop
2. Instructions to separate photos from the background in Photoshop
3. How to sharpen images in Photoshop in 2 ways

I wish you all success!

You finished reading the article "**How to delete Adobe Creative Cloud when installing Photoshop**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.