

How to delete the link, remove Hyperlink in Word

When you want to delete the entire link, the Hyperlink available in Word manually each link will take a lot of time. So how to quickly disable links on Word?

Many times you need to edit the copy of Word content on the network, delete all links in the text link. If the number of Hyperlinks on Word is small, we can do it manually, click Remove Hyperlink at the link. However, if multiple pages of text and multiple links are available, manual deletion is not feasible. So how to quickly delete all Hyperlink in Word documents? The following article will show you how to delete the entire link, remove Hyperlink on Word.


1. Instructions on how to create Hyperlink in Excel
2. This is a simple way to find and delete Hyperlink in Excel
3. How to create Hyperlink to link spreadsheets in Excel

Instructions to disable Hyperlink in Word

Method 1: Delete Hyperlink with Visual Basic code

Step 1:

At the interface of the Word document to delete the link, highlight the text and press **Alt + F11** .



Step 2:

The Microsoft Visual Basic interface appears. Here you click on the **Insert** tab and then select **Module** in the drop down list.




Step 3:

Appear interface to enter command. Please enter the code below into that interface.

```
Sub Remove_Hyperlink_KoDZ ( )
Dim i As Long
For i = ActiveDocument.Hyperlinks.Count To 1 Step -1
ActiveDocument.Hyperlinks (i) .Delete
Next I
```

End Sub




Step 4:

Then click on the **Run Sub / User Form** item at the Run or F5 key to execute the Module command.



When we return to the text we will see the entire link that was inserted into the content has been completely removed, the font format and color remain the same.

This method will be applied on Word versions so you can use it even with Word 2003.



Method 2: Delete the Word link link with the key combination

First, turn off Vietnamese typing tools like Unikey is open on your computer.


Then also black out the entire text to remove the link and press **Ctrl + Shift + F9** . Immediately all link links on Word will be deleted. This way we can also apply to versions of Word.




Method 3: Use the AutoCorrect feature

Step 1:

To disable (disable) hyperlink in **Word**, first click on the **File** tab.




In the options in the left pane, select **Options** .




Step 2:

Now on the screen that appears the **Word Options** dialog box, click on the **Proofing** option in the list of items in the left pane.




In the **AutoCorrect options** section, click the **AutoCorrect Options** button.




Step 3:

On the screen that appears the **AutoCorrect** dialog box, click on the **AutoFormat As You Type** tab.




In the **Replace as you type** section , check the **Internet and network paths with hyperlinks** section to deselect.


Then click **OK** to save the changes and close the dialog window.



Back in the **Word Options** dialog box, click **OK** to close the dialog window.



After you have disabled hyperlink:



See more:

1. Enter the serial number and the automatic initial character MS Word
2. Create a quick dot (.....) line in Microsoft Word
3. 8 tips or handling columns in Microsoft Word

Good luck!

You finished reading the article "**How to delete the link, remove Hyperlink in Word**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.