

How to disable Windows 10 Creators Update ads

The state of ads appearing continuously is still an annoying issue even on the new version of Windows 10 Creators Update. So how to completely disable the types of ads on Windows 10 Creators Update?

When upgrading computers to the latest version of Windows 10 Creators Update, users will be able to use a lot of new features as well as upgrade than previous operating system versions. However, a problem exists in all previous versions of Windows and this new version of Creators Update is the status of ads that appear everywhere, making users quite uncomfortable. As soon as we start the computer, we will see some ads appear Lock Screen. So how to completely disable all ads on Windows 10 Creators Update version?

1. Download Windows 10 Creators Update


1. Turn off ads at Share Dialog:

Share Dialog is a new feature that Windows 10 Creators Update provides for File Explorer. Accordingly, we will send any file or data to someone through the previously installed application, making sharing easier.

In addition, users can also find a number of other useful applications from Windows Store, when ads appear in the interface of this feature. So what if I want to remove the ads to install apps at Share Dialog?


Step 1:

First, open File Explorer and click on any file. In the menu above the interface will appear optional tabs for the file, click on the tab with **the Share icon** and then click on the option **Share**.




Step 2:

You will then see the new dialog interface with the shared application options we have installed, along with some suggestions for installing applications from Microsoft. Here, right click on the suggested application and **uncheck the Show apps suggestions option** .




2. Suggestions for application in Windows Ink:

Windows Ink is a feature that brings smoother experiences when you use a digital pen. However, when you access Windows Ink from the taskbar, it will suggest Suggested to advertise some of the installed applications.




Step 1:

First, you need to go to **Settings** and select **Devices** .



Step 2:


In the list of options on the left of the screen interface, click on **Pen & Windows Ink** . Look at the right interface and then **push the horizontal bar to the left** at the option **Show recommended app suggestions** , to turn off the feature of installing application on Windows Ink.



3. Turn off the Action Center ad:

Step 1:


First of all, we will type **keywords Notifications and actions settings** into Cortana and click on the search results.



Step 2:

Soon the Settings app will open and bring you to Notifications & actions settings. Here, we will find the **Get notifications from apps and other senders option** and switch to **Off mode** .


You do the same with the options after **Show me the Windows welcome experience after updates and sometimes when I sign in to highlight new and suggested** and **Get tips, tricks, and suggestions as you use Windows** .



4. Disable ads in File Explorer:


Step 1:

We will open **File Explorer** and then go to **View> Options> Change folder and search options** .



Step 2:


The **Folder Options** dialog box appears. Continue clicking on the **View tab** and then **uncheck the check box** at the option **Show sync provider notifications** . Finally click **Apply** and **OK** to save the changes.



5. Advertise at the Lock Screen screen:


Step 1:

We will go to **Settings** and then find **Personalization** .



Step 2:


In the list of options on the left side of the interface, users click on Lock Screen settings, then change the **Background** option to **Picture** or Slideshow. After that, we will turn off the option to **Get fun facts, tips, and more from Windows and Cortana on your lock screen** .



6. Turn off advertising at Start Menu:


Step 1:

We also access **Personalization from Settings** . Then select the **Start** setup group.



Step 2:

In the Start interface, users find the option **Occasionally shows suggestions in Start** and switches to **Off mode** by swiping the horizontal bar to the left.



7. Office application installation ads:


Step 1:

We will access the **System** section in the Settings interface.



Step 2:

Click on **Notifications & Actions settings** on the options list on the left. You look to the right and go to **Get notifications from these senders**. App appearances will receive ads on the system. If you want to remove all ads, users should **push the horizontal bar to the left at all applications**, switch to Off mode to not receive ads from the application.



Above is a guide to turning off all types of ads that appear on Windows 10 Creators Update versions. Advertising that appears constantly or more or less will cause discomfort to users, especially in the process of using our computers. Therefore, you should disable ads to fully experience the new features on Windows 10 Creators Update.

Refer to the following articles:

1. How to enable Dynamic Lock in Windows 10 Creators Update
1. Attractive features on Windows 10 Creators Update
1. 7 ways to do, customize in post will help your Windows 10 "as fast as wind"

You finished reading the article "**How to disable Windows 10 Creators Update ads**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.