

# How to fix the error can not open the Start Menu on Windows 10

The common mistake we see on Windows 10 is that it doesn't open the Start Menu through keyboard shortcuts and through Clicks. Software tips will guide you how to fix the error of not opening the Start Menu on Windows 10.


On Windows 10 operating system there are still some hidden errors and they often arise during use affecting the user camp. The common mistake we see on Windows 10 is that it doesn't open the Start Menu through keyboard shortcuts and through Clicks. In this article, Software Tips will guide you how to fix the error of not opening the Start Menu on Windows 10.




## 1. Restart the Windows service

Restarting Windows Services is the most effective way because they will reactivate Windows just like when you first started it.

**Step 1:** You press **Windows + R** to open the **RUN** window . Then, you enter **Services.msc** and click **OK** to open.




**Step 2:** Next, navigate to **Application Identity** and click **Start** to restart the Windows service.



## 2. Scan for errors through the Command Prompt


Command Prompt will help you scan for errors and handle errors automatically quickly, most effectively.

**Step 1:** You proceed to open **MenuStart** and enter **Cmd** to open **Command Prompt**. Remember to select **Run as Administrator** to open as an administrator.



**Step 2:** Next, you enter the command `sfc / scannow` to scan.

`sfc / scannow`




The system will automatically scan and fix errors for you.


### 3. Restart Windows Explorer

How to restart Windows Explorer will help your computer reactivate Windows system, work more stably.

**Step 1:** You proceed **Right-click MenuStart** and select **Task Manager** .



**Step 2:** Then, you proceed to find **Windows Explorer** and **right-click** and select **Restart** to restart.




## 4. Log back into your Windows account

Since we cannot access MenuStart, we are forced to log out using the key combination.

**Step 1:** You press **Ctrl + Alt + Delete** and select **SignOut** .


**Step 2:** Then, you proceed to re-enter the Windows password to login again.




## 5. Use the MenuStart bar full screen

On Windows 10, the MenuStart bar can be used full screen or a small corner as default. If you do not activate MenuStart then you can switch to large MenuStart.

**Step 1:** Have you conducted through open Settings shortcut **Windows + I** . Then, you choose **Personalization** to set up the interface.




**Step 2:** Next, navigate to the **Start** section and select **Use Start full screen** . Finally, try opening the **Start Menu again** to check it out.




## 6. Update Windows to the latest version

**Step 1:** You proceed to press **Windows + I** to open **Settings**, then you select the item **Update & Security** to check for updates and settings.



**Step 2:** Next, you select **Check updates** to check for updates. When the update is done check it out, install it.



In this article, Software Tips showed you how to fix the error of not opening the Start Menu on Windows 10 quickly and effectively. Good luck!

You finished reading the article "**How to fix the error can not open the Start Menu on Windows 10**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.

---