

How to install and uninstall fonts on Windows 11


In addition to the built-in fonts, you can also install custom fonts for Windows 11 to expand your font selection. Below is a guide on how to install Windows 11 fonts and how to remove fonts when you no longer need them.

Besides the built-in fonts, you can also install fonts for Windows 11 to expand your font selection. Once you successfully install fonts on your computer, all installed applications, such as Microsoft Office suite, Paint, etc., will be able to use those fonts. Below are instructions on how to install Windows 11 fonts and how to remove fonts when you no longer need them.

Instructions on installing fonts for Windows 11

Download the font installer from internet sources to your computer and then extract it. Next, click on the font and **select Install** to begin the installation process.


Once successful, the font has been installed on the computer.



Instructions on how to uninstall fonts on Windows 11


Uninstall the font in Settings.

Go to **Settings**, then select **Personalization** on the left, then look to the right and **select Font** to adjust it.



Scroll down and you'll see a list of fonts installed on your computer. Now, **enter the font you want to delete into the search box** . **Click the three-dot icon** next to the font and **select Uninstall** .


The font uninstallation process was then initiated.



Remove fonts from the Microsoft Store in Settings.

If you installed fonts from the Microsoft Store, follow these steps.

Open Settings, then tap on **Apps** , and to the side select **Installed apps or Apps & features** .




Then, locate **the font you downloaded from the Microsoft Store** , tap **the three-dot icon** , and select **Uninstall** to remove it.

How to remove fonts from the Control Panel in Windows 11

We open the Control Panel on the computer and then **click on the** Fonts option to access the system fonts.

Next, open the font management interface in Settings so you can delete fonts directly from there.



Remove fonts from Windows File Explorer

You can access the font management folder installed on your computer by going to the path **C:WindowsFonts** .

Next, **find the font you want to delete** from your computer, then click **the Recycle Bin icon** to delete it.

Metadata	
Full name	1FTV Dexurita
Font file	C:\USERS\DELL\APPDATA\LOCAL\MICROSOFT\W \DEXURITA.OTF
	<input type="button" value="Uninstall"/>
Version	Version 1.000
Designer/Foundry	Dora Typefoundry
Manufacturer	Dora Typefoundry
Copyright	Copyright (c) 2024 by Dora Typefoundry. All right
Legal trademarks	Dexurita is a trademark of Dora Tvpefoundry.

You finished reading the article "**How to install and uninstall fonts on Windows 11**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.
