

How to manage Tenda router remotely


Sometimes, we need to manage routers in remote offices, you can absolutely find this function in Remote WEB Management settings (Remote WEB Management settings).

Q: Why do we need to configure remote router management (Remote Management)?

Answer: Sometimes, we need to manage routers in the remote office, you absolutely can find this function in the **Remote WEB Management settings (Remote WEB Management settings)** .

For wireless routers

The topology can be visualized as follows:




Steps to proceed:

Step 1: Log in to the router's management page.

Step 2: Click on **Security Settings, Remote Web Management** (**Security settings, Remote Web Management**) in the top menu bar of the management page.

For example, if you want to manage the remote router with a device with an IP address of **110.110.110.110**, you can configure the router as follows:




After installation, the computer with the IP address **110.110.110.110** was able to manage the router remotely.

Just type: **http:// Router: 8080 WAN IP address** in the address bar and you can now log into the router's management page and manage it remotely.

For 3G router

The topology can be visualized as follows:




Steps to proceed:

Step 1: Log in to the router's management page.

Step 2: Click on **Security settings, Remote web management (Security settings, Remote Web Management)** . Check the **Enable** box in the **Remote Web Management** section to enable this feature to take effect.

For example, if you want to manage your 3G router remotely using an IP **202.96.134.33 - 202.96.135.205 device**, you can configure the router as follows.



(first). Click **Enable** to enable the Remote Web Management feature.

(2). Enter the management port number.

(3). Enter **WAN IP address** that can manage the router remotely.

(4). Remember to click **Apply** to save the settings.

After installation, if your IP address is between **202.96.134.33 - 202.96.134.205**, you can manage your router remotely. Just enter **http:// router: 8080 WAN IP address** in the address bar, for example:

http://110.25.36.26:8080, then you can log into the router's management page and manage it remotely.

General note:

1. When you use a public IP address specifically as the remote management IP address, you can only connect to this device remotely with the computer using this specific IP address.
2. It is best to change the default username and password when Remote Management is enabled, especially when you enter 0.0.0.0 as the remote web management IP address.

See more:

1. How to use VPN Gate fake IP to stabilize the Internet
2. Fake IP, IP change software, best anonymous surfing
3. Use Remote Desktop to access computers in the office and home networks
4. Tips for setting up Wi-Fi networks useful

You finished reading the article "**How to manage Tenda router remotely**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.