

How to reset Windows Security apps in Windows 10

If Windows Security crashes or fails to open, you can reset and / or reregister the Windows Security application to fix the problem. This guide will show you how to reset and re-register Windows Security app in Windows 10.

Windows 10 includes Windows Security, which provides the latest anti-virus protection. Your device will be actively protected from the moment Windows 10 starts up. Windows Security continuously scans for malware, viruses, and security threats.

In addition to this real-time protection, updates are downloaded automatically, helping to keep your device safe and protect them from threats.


If Windows Security crashes or fails to open, you can reset and / or reregister the Windows Security application to fix the problem.

This guide will show you how to reset and re-register Windows Security app in Windows 10.

Reset the Windows Security app from the Start menu

Step 1. Open the Start menu .

Step 2. Right-click or press and hold Windows Security on the Start list, click More and select App settings.



Step 3. Click the Reset button in Settings.



Step 4. Click Reset to confirm.

Step 5. Now you can close Settings if you want.

Reset the Windows Security app in PowerShell


Note : This option is only available starting with Windows 10 build 20175.

Step 1. Open Windows PowerShell.

Step 2. Copy and paste the below command into PowerShell and press Enter.

```
Get-AppxPackage *Microsoft.Windows.SecHealthUI* | Reset-AppxPackage
```

Step 3. When done, you can close PowerShell if you want.



```
Windows PowerShell
Copyright (C) Microsoft Corporation. All rights reserved.

Install the latest PowerShell for new features and improvements! https://aka.ms/PSWindows

PS C:\Users\Brink> Get-AppxPackage *Microsoft.Windows.SecHealthUI* | Reset-AppxPackage
PS C:\Users\Brink>
```

Install and re-register the Windows Security application in the Command Prompt

Step 1. Open Command Prompt.

Step 2. Copy and paste the following command into the Command Prompt and press Enter.

Code:

```
PowerShell -ExecutionPolicy Unrestricted -Command "& {$manifest = (Get-AppxPacka
```

Step 3. When done, you can close the Command Prompt if you want.

You finished reading the article "**How to reset Windows Security apps in Windows 10**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.