

# How to resize the Windows 11 Taskbar


Adjusting the size of the Taskbar can expand the screen space, making it easier to see the icons.

The default Taskbar size in Windows 11 may not suit your preferences or screen resolution. Adjusting the Taskbar size can free up screen space, making it easier to see icons. Windows 11 allows users to change the Taskbar size through several methods, as detailed in the guide below.

## Resize the Windows 11 Taskbar via Registry Editor

### Step 1:


Press the **Windows + R** key combination to open Notepad , then type "regedit" in the interface.



### Step 2:


In the next interface, navigate to the following path.

HKEY\_CURRENT\_USERSoftwareMicrosoftWindowsCurrentVersionExplorerAdvanced



### Step 3:

Right-click on the empty space in the right pane, select **New**, and then click on **DWORD (32-bit) Value**.



We will name this new value **TaskbarSi**.


| Name                | Type       | Data                    |
|---------------------|------------|-------------------------|
| TaskbarAI           | REG_DWORD  | 0x00000000 (0)          |
| TaskbarAnimatio...  | REG_DWORD  | 0x00000001 (1)          |
| TaskbarAutoHide...  | REG_DWORD  | 0x00000000 (0)          |
| TaskbarBadges       | REG_DWORD  | 0x00000001 (1)          |
| TaskbarDa           | REG_DWORD  | 0x00000000 (0)          |
| TaskbarFlashing     | REG_DWORD  | 0x00000001 (1)          |
| TaskbarMn           | REG_DWORD  | 0x00000000 (0)          |
| TaskbarSd           | REG_DWORD  | 0x00000001 (1)          |
| TaskbarSizeMove     | REG_DWORD  | 0x00000000 (0)          |
| TaskbarSmallIcons   | REG_DWORD  | 0x00000000 (0)          |
| TaskbarSn           | REG_DWORD  | 0x00000001 (1)          |
| TaskbarStateLast... | REG_BINARY | 43 c7 d8 67 00 00 00 00 |
| WebView             | REG_DWORD  | 0x00000001 (1)          |
| WinXMigrationL...   | REG_DWORD  | 0x00000001 (1)          |
| TaskbarSi           | REG_DWORD  | 0x00000000 (0)          |

#### Step 4:

Double-click the newly created value on the Taskbar and set its data to one of the following values:

1. 0 is for small taskbar icons.
2. 1 is for medium-sized taskbar icons (default).
3. 2 is for large taskbar icons.


Click OK and restart your computer for the changes to take effect.



## Resize the Windows 11 Taskbar via resolution.

#### Step 1:

Right-click anywhere on the desktop and select **Display settings** from the context menu.




## Step 2:

In this interface, under **Scale & Layout**, you'll find options to change the percentage. Decreasing the percentage (for example, from 125% to 100%) will shrink the icons on the Windows 11 Taskbar and overall interface elements, giving you more screen space. Conversely, increasing the percentage will enlarge the taskbar icons and interface.



Additionally, you can adjust the screen resolution to indirectly affect the Taskbar size. Increasing the resolution makes the elements smaller, while decreasing the resolution makes them larger.



You finished reading the article "**How to resize the Windows 11 Taskbar**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.