

How to turn off the Win 10 password - Uninstall and delete the Windows 10 password

How to turn off the Win 10 password - Remove and delete the Windows 10 password. If your computer does not need to be secure or you do not want to lose time each time you log in the computer to enter the password, then remove the password. Password is essential.


Setting a password will help increase the security for our computer from being snooped on by others. However, if your computer does not need to be secure or you do not want to spend time each time you log in the computer to enter a password, then removing the password is essential. The following article of TipsMake.com will guide you to remove the password on Windows 10, please refer.




On Windows 10, there are two main login methods: login with Microsoft account and login with Local Account so we have 2 ways to remove password for the two login methods above.

1. Uninstall Windows 10 password using Microsoft account


Step 1 : Open Settings and select **Accounts**



Step 2 : In the new window, select **Sign in with a local account instead**



Step 3 : A new window appears, enter the account password you are using on the computer and click **Next** .



Step 4 : In the next window, Windows will ask you to create a Local account to log in to the computer. However, because we want to remove the password, you do not need to enter the password in the Password box but click Next.

← Switch to a local account

Enter the following information. You'll sign in to Windows with a local account from now on.

If you sign in to Windows with a PIN or Windows Hello, you must set up a password to continue using them.


Username	<input type="text" value="Admin"/>
Password	<input type="password"/>
Re-enter password	<input type="password"/>
Password hint	<input type="text"/>

ThuThuatPhanMem.vn




<input type="button" value="Next"/>	<input type="button" value="Cancel"/>
-------------------------------------	---------------------------------------

Step 5: Click Sign out and finish is done.




2. Uninstall Windows 10 password using Local Account


Step 1 : You also open **Setting** and go to **Accounts** as above above in the new window, select **Sign-in options** and then on the right of the Password section window, click **Change**



Step 2 : A new window appears, enter the password you are using on the computer and click **Next** .



Step 3 : In the next window, leave the password blank and click **Next** .



At the last window you click Finish is done.

So with just a few simple steps, we can successfully remove the password on windows 10. Thank you for following the article.

You finished reading the article "**How to turn off the Win 10 password - Uninstall and delete the Windows 10 password**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.