

How to uninstall Windows 10 April 2018 Update

Windows 10 April Update is released to users but there are still some limitations, or your computer has problems, you can uninstall and return to the previous Windows version.

Windows 10 April Update launches users with new features, or upgrades with available features. However, there are some errors, such as crashes, when opening Google Chrome, or some other application. Or some computer cases are not stable and smooth when upgrading Windows 10 April Update. In these cases, users can consider removing Windows 10 April Update, then return to the previously installed Windows version.

The following article will show you how to uninstall Windows 10 version of April Update, return to the old version of Windows installed before updating.

1. Fix some errors before and after upgrading Windows 10 April 2018 Update
2. Error 0x8007042b when updating Windows 10 April 2018 and how to fix it
3. How to fix DefaultUser0 for installing Windows 10 April 2018 Update

Instructions for uninstalling Windows 10 April Update


Note to readers, to return to the previous Windows version, unused computers feature Storage sense, with the Previous Windows installation option (s) delete the old Windows 10 backup to free 10-20 GB of disk space. Storage sense will be accessed under **Start > Settings > System > Storage**.

Please refer to Storage Sense on Windows 10 Spring Creators Update according to the article below.

1. How to use Storage Sense on Windows 10 Spring Creators Update




Or if your computer does not have a **Windows.old** folder , it is not possible to return to the previous Windows version according to the steps below.



If checked and not deleted, follow the following procedure to remove the update April Update.


Step 1:

Go to **Start> Settings> Update & Security** on the computer.




Step 2:

Switch to the new interface and click on **Recovery** in the list on the left and look to the right, you will see the message **Go back to the previous version of Windows 10** . If the previous version you installed is Windows 7/8 / 8.1, the words Go back to Windows 7/8 / 8.1 will appear.




Step 3:

Now the system will ask you **why** you **want to remove** the Windows 10 April Update version to return to the previous Windows version, then select and **click Next** below.




Step 4:

What is the **Check for updates** interface ? , click **No, thanks** to continue.




You will then be presented with some **information about uninstalling** Windows 10 April Update, click the **Next button** .




Step 5:

If you use a password to log in to the previous Windows version, be sure to remember the password, click **Next** to continue.



Step 6:

Finally click **Go back to earlier build** to return to the previous Windows version.



Windows will then proceed to restore the previous Windows version. Although restoring this system will not lose data, but users also need to back up important data. Some configurations in the Settings section or some applications will need to be reinstalled.

See more:

1. The features will be removed on the Windows 10 April update 2018 Update
2. Windows Defender in Windows 10 April 2018 Update What's new?
3. Microsoft Edge tips on Windows 10 April 2018 Update

I wish you all success!

You finished reading the article "**How to uninstall Windows 10 April 2018 Update**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.