


How to unlock a Chromebook using an Android phone


Don't want to enter your password every time you open your Chromebook? If you own an Android phone, you can unlock your computer right from your phone. In the article below, TipsMake will guide how to unlock Chromebook on Android.

Before unlocking your Chromebook with an Android phone, you must first connect the two devices. Note that this feature is only available on phones running Android 5.1 and up, with Chromebooks running at least Chrome OS 71. In addition, Android phones and Chromebooks must also be signed in to the same Google account.

Next, on your Chromebook, click on the status section in the lower right corner of the screen, where it shows Wifi and battery status. On the next page, select the settings icon to enter the **Settings** menu .



Scroll down to the **Connected Devices** section and select **Set up** next to the **Android Phone** option .



In the pop-up window, select your Android phone from **Select A Device** . Next, select **Accept & Continue** at the end.

Connect to your phone

Your Chromebook and Android phone work better together. Connect them so you can text from your computer, share your internet connection, and unlock your Chromebook with your phone.* [Learn more](#)

Select a device

Google Pixel 3



*Features vary by device

When you connect your devices, you agree that your Chromebook can:

Send you notifications and default to remembering this computer for Messages. [Learn more](#)

Automatically install apps

Offer new features as they become available

Cancel

Accept & continue

On the next page, log in to Google, then the **All Set** confirmation window will appear. Click **Done** to close the window.




All set!

Go to [Settings](#) to see options for your connected phone



Done

Back in the Chromebook's **Settings** menu , find the **Verify** option under the **Connected Devices** section . Next unlock the Android phone if it's locked. You will get an alert on Chromebooks and Android phones with both devices connected.



Go back to **Settings**> **Connected Devices** on your Chromebook and select your Android phone. Turn on **Smart Lock** and enter your Chromebook password.

← Google Pixel 3

Enabled

 **Smart Lock**
Unlock your Chromebook with your phone. [Learn more](#)



Lock your Chromebook to check if Smart Lock works by long pressing on any button on the keyboard.

Once unlocked with an Android phone, the lock icon next to the password box changes from orange to blue. As such, the process has been confirmed. All you need to do is click your avatar to unlock your Chromebook.

You finished reading the article "**How to unlock a Chromebook using an Android phone**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.
