

# How to update drivers windows 10

Have you just installed Windows 10 and your computer is missing drivers? Or have you installed an automatic driver for your computer, but your computer lacks a driver? Please rest assured because you can use the Windows Update driver to update the Windows 10 driver automatically.

This method does not require you to download any software or driver files. You simply turn on your computer and use this win 10 driver update method.

## How to auto update drivers win 10


### 1. Turn on Windows Update

To perform the automatic updater driver win 10, first of all, you need to make sure your computer has turned on the Windows Update function. If not, you can follow the instructions below.

First go to Windows search box and type **services** . Then press Enter to open the Windows Services window.




When the Services window opens, find the Windows Update line near the bottom of the list. Then double-click the left mouse button to open Windows Update.




Find the Windows Update line to turn on Update


The Windows Update window opens. You can see on your computer it has the word Disabled which means it is disabled. You click on it to change.



Change the Windows Update mode from Disabled to Manual. You choose the Manual line.



Finally, click OK to save the above changes. So you have finished turning on Windows Update function on Windows 10.



## 2. Update driver win 10 automatically

There are 2 ways to update driver automatically win 10.


The first way is to partially update the driver win 10. That means the computer lacks any driver, you just update that driver. You can use this method to update drivers with a yellow exclamation mark.

The second way is to enable full Windows updates. This is the answer to the question, does Windows 10 automatically recognize the driver? Then the computer not only updates the missing driver, but also updates other Windows updates. This is the reason why Win 10 recognizes the driver itself as we often see.


However, I recommend this method should only be done on win 10. Win 7 is completely different. Updating the driver for Windows 7 through Windows Update will be much more prone to errors. You should not do how to update the driver for Windows 7 with Windows Update.

## 3. How to partially update the Windows 10 driver

The first step to partially update the Windows 10 driver is to right click on the computer icon (This PC) and select Manage.




The first step to perform how to update driver Windows 10 open part Manage  
When Computer Management opens, select Device Manager.




Continue to select Device Manager

In the list of drivers, select the driver that you need to update. These drivers, if missing, will have an exclamation mark. Staying on my computer, though not an update yet, is not without a driver. There should be no yellow exclamation mark.




Select the driver to install

Here I want to update drier discrete video card for laptop. I select NVIDIA Quadro K1100M series, left click and select Update driver.




Right-click the driver to install and select Update driver

The computer will give you 2 options. The first option is to find and update drivers from the internet. The second option is to update from an existing file on your computer. Please choose the first option.



Then you select the line Find and update the driver

Then the computer will find and update the driver automatically for you. You just have to wait for the driver to be updated.




The computer is automatically downloading and installing the driver


#### **4. How to update the whole Windows 10 driver**

If you have just installed Windows 10, then there will be a lot of drivers missing. If you use the way to update the driver win 10 in part as above, it will take a lot of work. You can update the Windows 10 drive all at once as instructed below.


First you need to open the Windows Settings window.




In the Windows Settings window, select the **Update & Security** function .



In Windows Update, the computer will tell us the status of driver updates. Click Install now to install the missing driver for the computer.



You can see that the computer is downloading the missing drivers.




## How to Install or Update the Best Windows 10 Driver!

### 1. Install the driver through Windows Update

This is one of the most reliable ways. Because the data packages during **Windows 10 Update** are checked and verified by Microsoft. It may take a while for hardware manufacturers to roll out an update on **Windows Update**, but this is still the simplest and most recommended way.

#### Perform:

1. Open Settings on Windows 10 using **Windows** key + **i**.
2. Select **Update & Security**.
3. Select **Windows Update**
4. Select **Check for updates**




After these steps, the **drivers** will be updated if the latest version is released from the hardware manufacturer. The system will automatically download and install.

## 2. Update Driver via Device Manager

**Device Manager** is part of system management, and it's available in **Windows 10** .


### Perform:

1. Step 1. Open **Start** .
2. Step 2. Search for **Device Manager** and select the first result
3. Step 3. Double-click on the hardware branch for which you want to update the driver
4. Step 4. Right-click on the hardware and select **Update driver**



*Update the driver via **Device Manager***

Step 5. Click **Search automatically for updated driver software**



*Automatically search and update Driver online*

After completing the steps, if a new update is available then Device Manager will download and install it automatically.


### 3. Use the updater from the device supplier.

In case the **Driver is** not available via **Windows Update** because it is too new or only available in beta. You will need **to manually download and install it from the manufacturer's website** .

You need to follow the manufacturer's instructions on their website. Usually, after completing the instructions you will download a file in the form of **' .exe'** and install them.


#### Perform:

1. Step 1. Open **Start** .
2. Step 2. Search for **Device Manager** and select the first result
3. Step 3. Double-click on the hardware branch for which you want to update the driver
4. Step 4. Right-click on the hardware and select **Update driver**



*Follow the same 4 steps of method 2*

Step 5. Click **Browse my computer for driver software**



*Update the driver via the manufacturer's website*

Step 6. Click **Browse**

Step 7. Select the main folder with your driver file and press the **OK** button

Step 8. Check the box **Include subfolders** to let the Wizard find the exact **.inf** file with the driver and click **Next**

Upon completing these steps, the wizard will detect and install new drivers on your computer.

#### **4. Update Graphics Card on Windows 10**


It's generally not advisable to update the driver unless it's necessary. Graphics manufacturers are always rolling out updates to improve the experience and assist with rendering and fixing problems with the game.

If you need the latest update for your graphics card, instead of waiting for **Windows Update**, you can use the **Graphics control panel** available from **Nvidia, AMD, and Intel** to download and install the latest drivers.

You can use the links below to download software corresponding to your brand:

1. [Nvidia GeForce Experience](#)
2. [AMD Radeon Software Adrenalin Edition](#)
3. [Intel Driver & Support Assistant](#)

After downloading the application corresponding to the Graphics Card, easy installation with *Next*.



*applications graphics control panel from the manufacturer after installation*

## Download the graphics card manually

One way to manually update the latest graphics card from the manufacturer is to download files from their web. Download link below

1. [Nvidia](#)
2. [AMD](#)
3. [Intel](#)

You finished reading the article "**How to update drivers windows 10**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.