

# How to upgrade Windows 10 Home, Single Language to Pro

In some cases, Windows 10 Home simply cannot compare to Windows 10 Pro, so how do you upgrade from Windows 10 Home to Windows 10 Pro? It's simple, just follow the steps below.

Microsoft offers several versions of Windows 10 for different purposes. Each version has a different price, and **upgrading from Windows 10 Home to Windows 10 Pro** (Windows 10 Pro being the highest-end personal version) depends on your needs. Windows 10 Pro offers many advantages over Windows 10 Home. This article will provide you with more information about Windows.



## Upgrade Windows 10 Home to Windows 10 Pro.

### Table of Contents:

1. Entering the Windows 10 Pro product key .
2. Reinstalling Windows 10 Pro .


## *Instructions on how to upgrade Windows 10 Home to Windows 10 Pro*

1. Enter your Windows 10 Pro product key.


To upgrade from Windows 10 Home to Windows 10 Pro, simply enter your Windows 10 Pro product key. The system will then automatically update you to Windows 10 Pro and unlock the necessary features.

One advantage of Windows 10 Pro is its ability to join domains, its policy features, and Hyper-V. To upgrade from Windows 10 Home to Windows 10 Pro using this method, you first need a product key. The rest of the process can be done by following the instructions below.


*Step 1:* First, press the **Windows + I** key combination to display **Windows Settings** > here, select **System** .




*Step 2:* Next, scroll down to the bottom and click on the "**About**" section .




*Step 3:* In this article, we used a machine that had already upgraded Windows 10 Home to Windows 10 Pro; however, the instructions are not affected as you just need to follow them. Here, click on **Change product key or upgrade your edition of Windows** .




*Step 4:* Next, select "**Change product key**" to enter your license key.




*Step 5:* Another menu will appear; you must now enter your license key for the system to verify.



*Step 6:* The system will ask you to confirm again. Click "**Activate**" to wait, and note that your network must be active.



Finally, you'll see a message saying "**Windows is activated** ." Simply close the window and restart your computer to complete the upgrade from Windows 10 Home to Windows 10 Pro.



## 2. *Reinstall Windows 10 Pro*

The other option is to reinstall Windows 10 on your computer. To install, you'll need a USB drive and the Windows 10 installation files. Fortunately, TipsMake has already provided instructions to help you quickly.

Refer to this guide on how to install Windows 10 ; this article will show you how to install Windows quickly and efficiently, as well as the necessary tools.

Although this method of upgrading Windows 10 Home to Windows 10 Pro takes more time, it's for those who can't meet the requirements of the method above but still want to use Windows 10 Pro.

Above, TipsMake has guided you through two ways to upgrade Windows 10 Home to Windows 10 Pro. Choose the method that best suits your situation. As you know, Windows 10 doesn't have a Policy, however, we can still

activate Gpedit.msc on Windows 10 Home. Refer to the instructions on how to activate Gpedit.msc on Windows 10 Home here and follow the steps.

You finished reading the article "**How to upgrade Windows 10 Home, Single Language to Pro**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.

---