

How to use Voicemod to change voice

In today's article, TipsMake.com.com will explain to you how to set up the Voicemod application and communicate or chat while gaming.

Voicemod is a voice changing software widely used when playing online games or chatting via applications such as Skype, Discord, etc.

In today's article, **TipsMake.com** will explain to you how to set up the Voicemod application and communicate or chat while playing games.

Note : First, close all communication programs before setting up an audio stream.

How to set up the Voicemod app

1. Download the Voicemod app and open it.
2. Go to **Settings** or wait for the initial setup to complete, if this is your first time running Voicemod.
3. Select your real microphone as the input device.
4. Select headphones as the output device.
5. Click **OK**.

At the bottom of the main window you have some toggle switches:

1. **Listen My FX Voice** will allow you to hear your own voice through headphones or earphones in real time.
2. **Voice Changer** will activate or deactivate voice effects.
3. **Ambient Sounds** will activate or deactivate background sounds.



To check if everything is working fine, enable all and choose a voice to play.

How to set up a communication app or game

In the above section, you have created a virtual microphone, through which you can send your converted voice anywhere you want. Here's what you have to do next:

1. **Voicemod** application must be open to provide virtual microphone.
2. Open your favorite communication app.
3. Go to **Settings**.
4. Find the **Audio section**.
5. Select **Voicemod Virtual Audio device microphone** as the input device.
6. Select headphones as the output device. It's done!

Important note!

If in your game/communication application audio settings you cannot select **Voicemod Virtual microphone** and only have the option to use the default system microphone, you must set **Voicemod Virtual microphone** as the default system microphone. (**Control Panel > Sound > Recording Tab > Set Voicemod Virtual microphone** as default device).

Do not use **the Voicemod Virtual Audio device** as an output, because we only need it as an audio bridge to do all the work. Through this output, you will hear the converted voice if the Voicemod app is open, while the rest

coming from the game or app remains the same.

If you don't want to use the Voicemod app to change your voice while chatting or gaming, you must:

1. Close the Voicemod application .
2. Open your favorite communication application.
3. Go to **Settings**.
4. Find the **Audio section**.
5. Set the real microphone as the input device.
6. Set the headset as the output device.

You finished reading the article "**How to use Voicemod to change voice**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.