


# Instructions automatic text carriage return in Excel - Auto line breaks when the width of the column in Excel

In Excel, when you type the content for a cell with long content, the letters will not automatically come down the line but be overwritten to the next column. The following article shows you how to automatically wrap text in Excel


When working with Excel files when you type content for a cell with long content, the letters will not automatically enter the line, but will be overwritten in the next column. The following article shows you how to auto-wrap text in Excel - Auto-wrap text at the end of the column width in Excel.

For example, when typing the text into cell C3 exceeds the width of the column so the text is obscured and not displayed:




# 1. For a cell that is an original cell (do not merge other column or row cells into 1), it is very simple:

- Select the cell you want to automatically drop text when the width of the column ends -> go to **Home** tab -> **Alignment** -> select **Wrap Text** feature :




- After selecting the option **Wrap Text** -> text content in the cell automatically down the line when the width of the column:



## 2. With data cells assembled from multiple cells


- The case with Excel cells is aggregated from many other cells if using **Text Wrap** feature to **wrap text** content when the column width is empty but the height of the cell does not change so the text is still covered. For example, when merging cell B4 and cell C4 into one cell after entering the content, selecting the **Wrap Text** feature does not automatically go down the line when the width of the column is over:




- In this case (the cells are aggregated from many other cells) you need to use additional code after selecting the **Wrap Text** feature :

+ Select the Excel file that you want to automatically move the text down the width of the column -> press **Alt + F11** to enter the command window -> copy the following code for the **Change** event of the worksheet:

```
Private Sub Worksheet_Change (ByVal Target As Range) Dim NewRwHt As Single Dim
```



+ After typing the above code to save and exit VBA, return to the Excel file to re-enter the content for the cell just created the text content automatically down the line when the width of the column and the height of the cell is changed. , unbleached text content:



The above is a detailed guide on how to auto-wrap text in Excel - Auto-break line at the end of the column width in Excel version 2016. I wish you success!

You finished reading the article "**Instructions automatic text carriage return in Excel - Auto line breaks when the width of the column in Excel**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.