

# Instructions to Delete Computer Password Win 7,8,10 Fastest

If you still don't know how to delete your computer password, please refer to this article. Hoang Ha PC would like to share with you how to delete passwords on Win 7, Win 8 and Win 10.

## How to delete computer password on win 10

With a few simple steps, opening your computer without entering a password will save you a lot of time. However, the disadvantage of a computer without a password is that the information security is not high. You should only delete the password when you are sure that you are working in a fairly safe environment. And below are the 2 most popular ways to delete a computer password on Win 10 that you should refer to.

### Remove computer password using Local Account

How to delete computer password using Local Account is one of the methods applied by many people because it has simple operations but brings high efficiency.

**Step 1:** Go to **Setting** and click ' **Account** '.

Picture 1 of Instructions to Delete Computer Password Win 7,8,10 Fastest

1. Next, you select ' **Sign-in Options** ' when the new window appears. Then, in the ' **Password** ' window, you click ' **Change** '.

Picture 2 of Instructions to Delete Computer Password Win 7,8,10 Fastest

**Step 2:** Another window will appear, you need to enter your current password in ' **Current password** ' and then press ' **Next** '.

Picture 3 of Instructions to Delete Computer Password Win 7,8,10 Fastest

**Step 3:** Leave all the boxes that require a password blank and continue to press ' **Next** '.

Picture 4 of Instructions to Delete Computer Password Win 7,8,10 Fastest

**Step 4:** Click **Finish** on the last window for the command to be executed.

## Remove Windows 10 computer password using Microsoft

Using Microsoft is one of the most convenient ways to remove your computer password. Depending on whether you have logged into your Microsoft account or not, choose one of the following two ways:

### Computer not logged in to Microsoft account:

**Step 1:** Use the key combination **Window + I** to open the ' **Setting** ' dialog box , then select ' **Account** ' .

**Step 2:** Click on ' **Sign-in options** ' , in the ' **Password** ' section, continue to select ' **Change** ' to change the password.

**Step 3:** After the new window appears, enter the current password of the **Local** account and click ' **Next** ' .

**Step 4:** In this window, leave all boxes blank and continue to click ' **Next** ' again to complete deleting the computer password.

### Computer logged in Microsoft account:

**Step 1:** Still use the key combination **Window + I** to open the ' **Setting** ' section, then select ' **Account** ' .

**Step 2:** Select ' **Your info** ' and continue to click ' **Sign in with a local account instead** ' .

**Step 3:** Enter your Microsoft account password and continue to press ' **Next** ' .

**Step 4:** Once a new window appears, you just need to fill in the ' **User name** ' field and skip all the remaining boxes and press ' **Next** ' .

**Step 5:** Click ' **Sign out and finish** ' .

## Quickly delete computer password on Win 7

If you are using a computer with Windows 7 operating system, please refer to the way to delete computer password that TipsMake provides below:


**Step 1:** Click on ' **Start** ' and select ' **Control Panel** ' .

Picture 5 of Instructions to Delete Computer Password Win 7,8,10 Fastest


**Step 2:** Click on ' **User Account and Family Safety** ' .

Picture 6 of Instructions to Delete Computer Password Win 7,8,10 Fastest

**Step 3:** After a new window appears, continue to select ' **Remove your password** ' in the ' **Make changes to your user account** ' section.



**Step 4:** Enter your current password and click ' **Remove Password** ' to delete the password.



## Instructions on how to delete computer password for Win 8

Setting a password for your Win 8 computer will help you secure important data, but in case you don't want to waste time entering a password or your computer doesn't have any important data that needs to be secured. Or simply your computer is just for entertainment, removing the password will be more convenient for you.

Below is how to remove computer password for Windows 8 that TipsMake wants to share with you.

**Step 1:** Use the **Windows + R** key combination to open the ' **Run** ' dialog box .

**Step 2:** After entering the **netplwiz** command , click ' **OK** '.

**Step 3:** In the ' **User Account** ' window , uncheck ' **User must enter a user name and password to use this computer** ' and continue to click ' **OK** '.

**Step 4:** When the ' **Automatically sign in** ' interface appears, just enter the current password in the ' **Password and Confirm Password** ' fields to confirm it again.

**Step 5:** After following the above steps, you need to restart your computer to complete the password removal.

You finished reading the article "**Instructions to Delete Computer Password Win 7,8,10 Fastest**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.

