

Macromedia Flash - Animation and rotation effects

Through this exercise, you will see how to create a nice rotating animation effect with just a few simple flash tips.

Through this exercise, you will see how to create a nice rotating animation effect with just a few simple flash tips. No need to use Action Script in this lesson, you still learn how to create a nice rotating image. With this tutorial, you can apply to create banner for website, or some suitable advertising photos.


Step 1

First you need to prepare an image to make the effect, you can save as to the following image if you do not already have the image on the machine.



Step 2

Create a new flash file, press **Ctrl + J** (Document Properties) and set the width to **300 px** and height to **225 px** , with the background color white. Set **Frame rate to 55** and click **OK** .



Step 3


Name the current layer as *picture* by double-clicking on the default name (Layer 1) and renaming. Press Enter after entering the new name.

Step 4

Go to **File > Import > Import to stage** (**Ctrl + R**) and import into the image you prepared in step 1.

Step 5


Select the imported image, press **F8** (Convert to Symbol) to convert it into a **Movie Clip Symbol** .



Step 6

Select the newly created Movie Clip (*picture*), go to the **Align Panel** (**Ctrl + K**) and select the following properties:

- Click the **To Stage** button in the Align / Distribute section
- Click on **Align horizontal center**
- Click on **Align vertical center**




Step 7

Click on frame 15 and 70 and press **F6** key on the keyboard respectively. While selecting frame 70, press F6 10 times. Then click on frame 100 and press **F6** key.


Step 8

While you're still on frame 100, take the **Free Transform Tool (Q)** and enlarge the image like this:




Step 9

After that, select the **Selection Tool** (V) and click once on the picture to select it. Go to the **Properties Panel** (**Ctrl + F3**), on the right you will see the **Color** menu. Select **Advanced** in this menu and click the **Settings** button, then set the following color ratios:



Step 10

Go back on frame 80 and go to the **Properties Panel** (**Ctrl + F3**). At **Tween** choose **Motion** , for **Ease** set to **100** and **Rotate** choose **CW** .



Step 11


Select frame 71 and press Delete key on the keyboard. Repeat this process for each frame 73,75,77 and 79.

Step 12

Go back on the first frame and repeat step 8


Step 13

After that, select the **Selection Tool** (V) and click once on the picture to select it. Go to the **Properties Panel** (**Ctrl + F3**), on the right you will see the **Color** menu. Select **Advanced** in this menu and click the **Settings** button, then set the following color ratios:




Step 14

Select the **Filters** tab on the left side of the Properties tab, click the plus icon (+) and select **Blur** . Then set the options as follows:



Step 15

Right-click anywhere on the gray area between the two keyframes on the timeline and choose **Create Motion Tween** from the menu that appears.



And finally, try running your product. Download the source file [here](#) .

You finished reading the article "**Macromedia Flash - Animation and rotation effects**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.