

Remove Network icon on Lock Screen lock screen Windows 10

Lock Screen Lock Screen on Windows 10 is the first screen that you see when you log in to your account. The lock screen has a lot of functions, such as using to set individual options, configuring a number of options such as configuring application status, customizing background wallpapers, activating Cortana to perform some Basic tasks when your computer is locked.

Lock Screen Lock Screen on Windows 10 is the first screen that you see when you log in to your account. The lock screen has a lot of functions, such as using to set individual options, configuring a number of options such as configuring application status, customizing **background** wallpapers, activating **Cortana** to perform some Basic tasks when your Windows 10 computer is locked.

Although Windows 10 allows users to disable the **Lock Screen lock screen** , the operating system will lack the option to delete certain functions, such as the Network icon in the bottom right corner. Allows users to view and disconnect devices with a Wifi network.

However, the good news is that you can manipulate to lock screen Lock Screen better without having to disable it. Just 'tweak' some settings on the operating system to remove the Network button on the Lock Screen lock screen and Sign-in screen, just like removing Power options.




Remove network icon on lock screen Lock screen


Important note :

You should **back up your entire computer** before performing it, in case of a bad situation.

1. Press the **Windows + R** key combination to open the **Run** command window.
2. On the Run command window, enter **regedit** and press **Enter** or click **OK** to open the **Registry Editor** window.
3. In the Registry Editor window, navigate to the key:
HKEY_LOCAL_MACHINE\SOFTWARE\Policies\Microsoft\Windows\System
4. Here you select the **System** folder, then in the right pane you right-click it and select **New => DWORD (32-bit) Value**.
5. Name this new **DWORD** as **DontDisplayNetworkSelectionUI** and then press Enter.




6. Double-click the DWORD you just created, then **change the value in the value data frame from 0 to 1**.



7. Finally **close the Registry Editor window** and **restart your computer** to complete the process.

Now on the Lock Screen lock screen, notice that there are no more network icons.



If you want to re-display the network icon on the Lock Screen lock screen, follow the same steps and change the value in the Value data frame from 1 to 0.

Refer to some of the following articles:

1. How to enable or disable SuperFetch on Windows 10/8/7?
1. Guide to quickly fix "Inaccessible Boot Device" error on Windows 10/8/7 and Windows Vista
1. How to disable 1 or more any key on Windows 10 keyboard?

Good luck!

You finished reading the article "**Remove Network icon on Lock Screen lock screen Windows 10**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.