

Small tips for adding background music when opening apps on Android

Background music often helps people to focus more on every task. It is like a catalyst that makes you feel comfortable even at the most stressful time. And if you are using an Android phone, this article will show you how to add background music to applications on Android.

Background music often helps people to focus more on every task. It is like a catalyst that makes you feel comfortable even at the most stressful time. And if you are using an Android phone, this article will show you how to add background music to applications on Android.

1. Simple way to recover deleted contacts on your Android device
2. 10 things to and should not do with Android devices
3. Fix common errors with Android devices

Then, when you open any application that you have added background music to before, you will be able to both work with the application and listen to your favorite tunes until you close the application.

First, download the APK file of **the Tasker application** and install it on the device (you will have 7 days of trial before deciding to buy it on Google Play), remember to choose the version that is suitable for the Android version I am using.

Tasker: Trial Download / Install



These versions should not be installed by users who have already installed the Play Store version. The expire after 7 days unless validated.

As of March 24th, 2013, it's only possible to validate the trial version with a key or Play Store order nu from a purchase before that date.


For older releases, see [here](#).


Download


Android Version	Tasker Version	Download	QR Code	Release Notes
ICS, JellyBean, KitKat, Lollipop	4.0+	4.7u3	Download	Release Notes
Donut, Eclair, Froyo, Gingerbread, Honeycomb	1.6, 2.0+, 3.0+	1.6u2	Download	Release Notes
Cupcake	1.5	1.0.11	Download	Release Notes


Please make sure you pick the right version for your Android OS version.

After installing Tasker on Android device, go to **Settings** -> **Accessibility** -> **Tasker** and turn **ON** to allow Tasker to use all the features on your device.










Now start the application and click on **the + sign** . Here you will be provided with a list of options for you to initialize the profile. This case is **Application** .





Click + to add a Profile.

Profiles link contexts (conditions) with the tasks that should run when the conditions are met.




Next, the list of applications installed on the device will appear. Click **All** to Tasker to display the entire list of applications. Now select an application that you want to add background music to. Here we will choose **Viber** application. Then press the back key to return to the main screen, click the name of the application you selected and click **New Task** .





Proceed to naming the task at will, for example **Music** . Then click the checkmark to save and click **the** + to set the action for this task




Viber On

Viber


Music ✓

New Task Name






Click + to add an Action.



The **Select Action** dialog box appears, enter the **Music Play** keyword and click the corresponding **Music Play** result. Next is the dialog box to set the location of the background music file you want. When you have finished navigating to the background music file location, check the **Loop** option so that the file plays repeatedly when the song is finished. After the setup is complete, press the **Back** key twice to return to Tasker's Profiles screen.






When you return to the Taskers Profiles screen, press and hold the name of the task you just created, then click the **Add Exit Task** option when the selection menu appears. The effect of this option is to set the stop playing background music when you exit the application on the Android device after you have finished working. Next, name the exit task. Here you can set **Music 2**, then click the check mark to save.


Viber On


Viber → Music

- Add Exit Task ◀
- Move To Exit ✂
- Select Different Task ☰
- Unlink Task ✕



You then do the action for this task again by clicking **the + sign** . And enter the **Music Stop** keyword into the search line and click on the corresponding option on the results frame.





On the next screen, you don't need to do anything, just leave it and press twice on the Back key to get back to Tasker's main screen. When in the main screen, press and hold the name of the profile you just created and select **Add > State** . This action will set the automatic stop playing background music when the device screen is off.




Viber On

Viber → Music


Add	+
Delete	🗑️
Name	A



1




Next click **Display** > **Display State** on the next selection screen.



On the next setting screen, select **ON** in the **Is** option. This option will allow the background music to be played again when the phone screen is turned on. Then press the **Back** key twice to return to the main Tasker screen.



And when everything has completed following the steps above, you will see the result as shown below.



That's it, now every time you start the application, you have set up the background music, the music will be automatically played.

Good luck!

You finished reading the article "**Small tips for adding background music when opening apps on Android**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.
