

Steps to fix error 0x8004FC12 on Windows 11

How to fix error 0x8004FC12 helps you successfully activate copyright on Windows 11 and fully use the features of the operating system. When you encounter this error, you will have to deal with them first before installing other software

Error 0x8004FC12 prevents you from activating copyright on Windows 11 and can not use the full features on the computer. When you encounter this error, you will have to deal with them first if you want to use Windows stably.

1. Windows 11 and license activation


The Windows 11 operating system is completely free to upgrade from Windows 10 and this means you will not have to activate or purchase a license if you already use a copyrighted Windows 10. However, some platforms encounter an error, you will have to reactivate the license from the beginning. The reactivation of Windows 11 license is similar to Windows 10, you just need to perform the same operations as on Windows 10.

On some computers, Windows 11 activation encounters error 0x8004FC12 and they cannot use the full features. The generation of errors on Windows 11 has caused many problems for users. Especially those who need a stable operating system. Error code 0x8004FC12 arises because of the Windows host system and makes it impossible for the system to enter the Active Windows code.


2. Fix error 0x8004FC12 with Troubleshoot

Troubleshoot is a debugging tool from Microsoft and they solve a lot of errors on the Windows operating system.


Step 1: Open the Start Menu (1) and select Settings (2) to open the settings on your Windows computer.




Step 2: Then, select the Update & Security tab to open the update and security feature.




Step 3: Next, select the Troubleshoot tab and select Additional troubleshooters to see the fixer on the computer.



Step 4: Find the Run the troubleshooter tab of the Windows Update section to fix error 0x8004FC12.




Step 5: You just need to wait for the system to handle the error and restart the computer when it's done. After a successful reboot, please re-enter the code to Active Windows 11.




3. Fix error 0x8004FC12 by turning off Firewall

The firewall on Windows 11 is also one of the main causes of not being able to Active Windows 11 on the computer.


Step 1: Open the Expand item on the Taskbar and select the Windows Defender item.




Step 2: Next, select the Firewall & network protection item to view the settings related to the firewall and network security.



Step 3: Then, select the Domain network / Private network / public network items in turn and turn off the Firewall feature.




Step 4: When you have finished turning off the firewall, proceed to reactivate Windows 11 according to the purchased key. At this point, the error code 0x8004FC12 will be gone.




4. Fix error 0x8004FC12 with Command Prompt

Step 1: Press the Windows + R combination to open the RUN window and enter Cmd to open the Command Prompt.



Step 2: Then, enter the following commands in turn and press Enter to process.

```
net localgroup Administrators localservice /add
```




```
Administrator: Command Prompt
Microsoft Windows [Version 10.0.19042.631]
(c) 2020 Microsoft Corporation. All rights reserved.

C:\Windows\system32>net localgroup Administrators localservice /add
The command completed successfully.

C:\Windows\system32>
```

fsutil resource setautoreset true C:




```
Administrator: Command Prompt
Microsoft Windows [Version 10.0.19042.631]
(c) 2020 Microsoft Corporation. All rights reserved.

C:\Windows\system32>net localgroup Administrators localservice /add
The command completed successfully.

C:\Windows\system32>fsutil resource setautoreset true C:
The operation completed successfully.

C:\Windows\system32>
```

netsh int ip reset resetlog.txt



```
Administrator: Command Prompt
C:\Windows\system32>net localgroup Administrators localservice /add
The command completed successfully.

C:\Windows\system32>fsutil resource setautoreset true C:\
The operation completed successfully.

C:\Windows\system32>netsh int ip reset resetlog.txt
Resetting Compartment Forwarding, OK!
Resetting Compartment, OK!
Resetting Control Protocol, OK!
Resetting Echo Sequence Request, OK!
Resetting Global, OK!
Resetting Interface, OK!
Resetting Anycast Address, OK!
Resetting Multicast Address, OK!
Resetting Unicast Address, OK!
Resetting Neighbor, OK!
Resetting Path, OK!
Resetting Potential, OK!
Resetting Prefix Policy, OK!
Resetting Proxy Neighbor, OK!
Resetting Route, OK!
Resetting Site Prefix, OK!
Resetting Subinterface, OK!
Resetting Wakeup Pattern, OK!
Resetting Resolve Neighbor, OK!
Resetting , OK!
Resetting , OK!
```

After completing the above commands, please proceed to restart the computer and check the error code 0x8004FC12 to see if it still appears when Active Windows 11 or not.

In this article, Tipsmake has shown you how to fix error 0x8004FC12 when Active Windows 11 quickly and effectively. Have a nice day!

You finished reading the article "[Steps to fix error 0x8004FC12 on Windows 11](#)" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.