

# This is how Windows 10 to Win 7 or Win 8.1 does not need to be reset

Many people after installing to Windows 10 version want to downgrade the device and return to Windows 7 and Windows 8.1. However, in addition to the whole computer we have any way? The answer is yes...


If you are using Windows 7 and Windows 8 will no longer see the proposed update to upgrade to Windows 10. Instead, the timer is updated and we will accidentally install Windows 10 without knowing it. This big action by Microsoft seems to have received no support from users, when installing automatic upgrade to Windows 10 version.

Many people consider reinstalling the computer to return to Windows 7 or Windows 8 operating system. However, do not rush to reinstall but can perform a simple and easier way to downgrade.

**Note, in order to be able to do this, your computer must be upgraded to Windows 10 within 30 days. And suitable for those who upgrade directly on Windows 7, Windows 8 or Windows 8.1. If you install Windows from a USB drive or a CD and delete the entire partition earlier, don't do it this way.**


## Step 1:

Click the Windows 10 icon under the Windows search bar, select **Settings** .



## Step 2:


Next, at the Settings interface, we will select the **Update & Security** item.



### Step 3:

Here, click the **Recovery** item. If you can downgrade your computer, you will see the option **Go back to Windows 7** or **Go back to Windows 8.1**.

These two options will appear depending on which operating system you used earlier. Next, click **Get Started** and follow the instructions.



The process of downgrade is fast or slow depending on the computer configuration. But looking at them is faster than upgrading.

When you downgrade to Windows 7 or 8, you need to change your Windows 7 password and don't use Windows 10 passwords anymore, if you have created a Microsoft account for the new operating system.

### Refer to the following articles:

1. 7 ways to do, customize in post will help your Windows 10 "as fast as wind"
1. How to open the virtual keyboard in Windows 10
1. Ways to turn off your computer on Windows 10

**I wish you all success!**

You finished reading the article "**This is how Windows 10 to Win 7 or Win 8.1 does not need to be reset**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.

---

© 2019 TipsMake.com