

# How to change the presentation mode for screens in Windows 10

Display Switch is used to change the presentation mode for the main screen of Windows 10 PC. This tutorial will show you how to change the presentation mode for monitors in Windows 10.

Display Switch is used to change the presentation mode for the main screen of Windows 10 PC, to show only on the **PC screen ( PC screen only )**, project the same content on the second screen ( **Duplicate** ), expand on all screens ( **Extend** ) or only the second screen ( **Second screen only** ).

This tutorial will show you how to change the presentation mode for monitors in Windows 10.

**Mode Description PC screen only** Only the current home screen is active. All other connected screens will be disabled. (When you are connected to a wireless projector, this option will change to **Diconnects** .) **Duplicate** The main screen will be duplicated on the second screen. **Extend** (default) The main screen extends across all connected displays and allows you to have a desktop spread across them. **Second screen only** The current home screen is disabled. All other connected displays will remain enabled and the second screen will be used as the new home screen.

## Change the presentation mode for the monitor in the Project flyout menu

1. Follow step 2 ( **Project** ) or step 3 ( **Action Center** ) below, depending on how you want to open the flyout Project menu.
2. Press the Win + P keys or swipe from the right edge of the touch screen and move to step 4 below.
3. Open **Action Center** , click the **Project** button and move to step 4 below.

## ACTION CENTER

No new notifications

**TenForums.com**

Open Action Center, click the Project button

4. Click the desired presentation mode ( **PC screen only**, **duplicate**, **extend** or **second screen only** ). You can also press the down arrow key until you see the projection mode you want and press Enter to apply.

For example, if you have a blank black screen and can't see the menu, you can do this below to restore default **Extend** settings.

Press the Win + P keys, press the down arrow key twice and press Enter .

## PROJECT



**TenForums.com**



[Connect to a wireless display](#)



Click the desired presentation mode

# Change the presentation mode for the screen with the command

Copy and paste one of the commands below that you want to use into the Command Prompt or the **Run** dialog box ( Win + R ) and press Enter .

## PC screen only

```
%windir%System32DisplaySwitch.exe /internal
```

## Duplicate

```
%windir%System32DisplaySwitch.exe /clone
```

## Extend

```
%windir%System32DisplaySwitch.exe /extend
```

## Second screen only

```
%windir%System32DisplaySwitch.exe /external
```

You finished reading the article "**How to change the presentation mode for screens in Windows 10**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.