

# How to delete Camera Roll and Saved Pictures folders in Windows 10


The Camera Roll and Saved Pictures folders come with Windows 10 by default. The following article will show you how to move, hide or delete these folders so that they do not interfere, as well as hide related libraries.

The **Camera Roll** and **Saved Pictures** folders come with Windows 10 by default. But if you don't use them, they won't make any sense. The problem is that you cannot delete them normally.

The following article will show you how to move, hide or delete these folders so that they do not interfere, as well as hide related libraries.

## Move Camera Roll and Saved Pictures folders

By default, the **Camera Roll** and **Saved Pictures** folders will be in the **Pictures** folder . You can easily move them to any other folder.



Move Camera Roll and Saved Pictures folders

You need to solve each folder in turn. Right-click on the folder and select **Properties**. Switch to the **Location** tab .

There is a field where you can enter the directory path for where you want the folder moved.


Don't worry if you don't know this link! Just click **Move .** , navigate in the destination folder of your choice and click on **Select Folder** . Finally, click **OK** to confirm the move.

You can return to this screen and click **Restore Default**> **OK** if you want the folder back in your **Pictures** .

Alternatively, you can simply cut ( **Ctrl + X** ) and paste ( **Ctrl + V** ) the folder somewhere with **File Explorer**.

## Hide the Camera Roll and Saved Pictures folders

If you don't want to move folders or delete them permanently, you can hide them from view.



Hide the Camera Roll and Saved Pictures folders

To do this, highlight both folders (or hold **Ctrl** as you click each one) and switch to the **View** tab on the ribbon. In the **Show / hide section** , click **Hide selected items** .

If you still see the folder but with the icon dimmed, that means you have the setting turned on to see hidden items. To turn off this feature, still on the **View** tab, uncheck **Hidden items**.

Reverting these instructions will allow the folders to show again.

## Delete the Camera Roll and Saved Pictures folders

Because the **Camera Roll** and **Saved Pictures** folders are tied to the **Camera** and **Photos** app, the only way to permanently delete these folders is to uninstall the apps.

These apps come with Windows 10 and can't be uninstalled like a regular program. Instead, you need to use PowerShell to uninstall.

To get started, perform a **PowerShell** search . Next, right click on the result and select **Run as administrator** .

Copy ( Ctrl + C ), paste ( Ctrl + V ) and press Enter on the keyboard for each command.

To uninstall Camera:

```
Get-AppxPackage *windowscamera* | Remove-AppxPackage
```

To uninstall Photos:

```
Get-AppxPackage *photos* | Remove-AppxPackage
```

Note that you can use the **Photos** app to browse photos on your computer without realizing it. A suitable alternative is **Windows Photo Viewer** .

If you want to reinstall those applications or any other deleted Windows applications, use this command in PowerShell:

```
Get-AppxPackage -AllUsers | Foreach {Add-AppxPackage -DisableDevelopmentMode -Reg
```

You finished reading the article "**How to delete Camera Roll and Saved Pictures folders in Windows 10**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.