


# How to delete the Ansel folder on the computer

How to delete the Ansel folder. The ansel folder only appears on computers with discrete Nvidia cards with the main purpose of saving high-quality screenshots and HDR images while playing games. What's special is when you delete this folder and it can reappear

If you accidentally check the User folder on your computer, you will see a strange folder with the name Ansel and wonder if deleting this folder affects your computer? Let's answer the above question in this article!

## 1. What is the Ansel folder?




The ansel folder only appears on computers with discrete Nvidia cards with the main purpose of saving high-quality screenshots and HDR images while playing games. Especially when you delete this folder and it may reappear, if you find this folder inconvenient and useless, please follow the instructions on how to delete it in this article.


## 2. Delete the ansel folder with the Ansel Configuration Utility

**Step 1:** Enter the following address in the address bar on **This PC / Computer** .


**C: Program FilesNVIDIA CorporationAnsel**



**Step 2:** Open the **NvCameraConfiguration.exe** application .




**Step 3 :** You navigate to the **NvCamera Status** and select **Disable (1)** => **Save (2)** .




**Step 4:** You go back to the ansel folder in the path **C: Users [your username ]**

Next, right-click the **ansel** folder (1) => **Delete** (2) and this folder will not appear again.




### 3. Delete the ansel folder with the cmd command

**Step 1:** You click on **Search** (1) => **cmd** (2) => **Run as administrator** (3) .




**Step 2:** Enter the following command and press **Enter** .

*RunDll32 "C: Program FilesNVIDIA CorporationInstaller2InstallerCoreNVI2.DLL", UninstallPackage Ansel*




**Step 3:** Enter the following command and press **Enter** .

`rundll32 "%PROGRAMFILES%NVIDIA Corporation\Installer2\InstallerCore\NVI2.DLL", UninstallPackage NvTelemetryContainer`



**Step 4:** Open the `ansel` folder in the path `C: Users [your username ]`

Next, right-click the `ansel` folder (1) => **Delete** (2) and this folder will not appear again.



Through this article, you already know what the `ansel` folder is for and how to delete it? Good luck!

You finished reading the article "**How to delete the Ansel folder on the computer**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.