

How to enable parallel download in browser

Does your browser take a long time to download large files? If this is the case, you can enable parallel download, which allows your browser to download a file in multiple threads, ultimately increasing download speed.


But what exactly is parallel downloading and how can you enable it in different browsers?

How to enable parallel downloads in Google Chrome


Google Chrome is the default web browser on most devices. If you want to use parallel downloads in Chrome, follow the instructions below.

On the computer

1. Launch Google Chrome, type **chrome://flags** in the search bar and press **Enter**.




2. Type **Parallel downloading** in the search bar and press **Enter**.
3. Click the drop-down icon next to Parallel downloading and select **Enabled** from the context menu.



4. Click the **Relaunch** button .

After that, Google Chrome will restart with parallel downloading enabled. If you want to disable parallel downloading in Chrome, select **Disabled** from the drop-down menu and restart Chrome.

On mobile



1. Open Chrome, type **chrome://flags** in the address bar and press **Enter**.
2. Type **Parallel downloading** in the search and press **Enter**.
3. Select **Enabled** from the Parallel downloading drop-down menu.
4. Press the **Relaunch** button .


After restarting, Google Chrome will use the parallel download feature every time you download a file from the Internet.

How to enable parallel downloads in Microsoft Edge

Similar to Google Chrome, you will have to use the Microsoft Edge flag page to enable parallel downloads on this browser. Here's a step-by-step guide on how to do that.


On the computer

1. Open Edge on your computer.
2. Type **edge://flags** in the search bar and press **Enter**.
3. Type **Parallel downloading** in the Flags site search bar and press **Enter**.
4. Select **Enabled** from the Parallel downloading drop-down menu.



Then, click the **Relaunch** button that appears. To disable parallel downloading in Edge, select **Disabled** from the Parallel downloading drop-down menu and restart the browser.

On mobile




To enable parallel downloads in Edge on Android, type **edge://flags** in the search bar and press **Enter**. Then select **Enabled** from the Parallel downloading drop-down menu and press the **Relaunch** button .

How to enable parallel downloads in Mozilla Firefox

It is very easy to enable parallel downloads in Mozilla Firefox. Follow the instructions below to do that:

1. Open Mozilla Firefox, type **about:config** in the search bar and press **Enter**.
2. Click the **Accept the Risk and Continue** button .



3. Type the following command in the search box and press **Enter**. This option controls the number of parallel connections allowed per server in Firefox.

```
network.http.max-persistent-connections-per-server
```

4. Click the **Pen** icon next to the option to modify its value. By default, the value is set to **6** , but you can increase this value up to **20** to increase the number of parallel downloads allowed, ultimately increasing download speed.



5. Click the **Check** icon . Then, restart Firefox to save the changes.


Unlike Google Chrome and other Chromium-based browsers, you cannot use parallel downloads in Firefox on Android.

How to enable parallel downloads in Brave

If you want more security, you must use Brave as your default web browser. However, if you want better download speeds, in addition to privacy, you must enable parallel downloads in Brave.


On the computer

1. Launch Brave, type **brave://flags** in the search bar and press **Enter**.
2. Type **Parallel downloading** in the search bar, select **Enabled** from the Parallel downloading drop-down menu and click the **Relaunch** button .



To disable parallel downloads in Brave, select **Disabled** from the drop-down menu and restart Brave.

On mobile



To enable parallel downloads in Brave on Android, type **brave://flags** in the address bar and press **Enter**. Then select **Enabled** from the Parallel downloading drop-down menu and press the **Relaunch** button .

You finished reading the article "**How to enable parallel download in browser**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.