

How to fix no low battery notification error on Windows 11


The sudden shutdown of the computer is often due to the lack of low battery notification. You can refer to some methods to fix the error of no low battery notification on Windows 11.

The computer suddenly shuts down due to the lack of low battery notification in Windows 11. This problem interrupts work, there is a risk of losing data when the computer suddenly shuts down, without charging the battery. You can refer to some of the troubleshooting methods below to fix the error of no low battery notification on Windows 11.

Check if low battery notification is turned on?


To get low battery notifications on Windows 11, you need to set up notifications on your computer. If you accidentally turn it off or set it up incorrectly, it will not appear on your computer. Please check your settings to see if you have enabled low battery notifications on Windows 11.

1. How to enable low battery warning on Windows 11




Check notifications on Windows 11 computer

Open **Settings** on your computer then **click on Notifications** to check notifications on your computer.



Now check if notifications are enabled on your Windows computer.



Update or reinstall the battery management driver

Step 1:

Press **Windows + X** key combination and select **Device Manager** from the list.

Installed apps

Mobility Center

Power Options

Event Viewer

System

Device Manager

Network Connections

Disk Management

Computer Management

Terminal

Terminal (Admin)

Task Manager


Settings

File Explorer

Search


Run

We expand the **Batteries** section , right-click on **Microsoft ACPI-Compliant Control Method Battery** and select **Update driver** .




Step 2:

Click **Search automatically for drivers** to find new drivers and install them.



If Windows reports the best driver is installed but the problem persists, right-click **Uninstall device** to uninstall it.


Restart your computer and Windows will automatically reinstall the driver.



Reset battery usage mode on Windows

You open Command Prompt as administrator, then type the command below and press Enter to launch.

This command resets all power usage modes to default settings, possibly restoring missing battery notification options.



You finished reading the article "**How to fix no low battery notification error on Windows 11**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.