

# How to fix the error Unikey disappears itself

Many people encounter Unikey errors that automatically disappear, don't start with Windows, and don't know where to find them. Software tips will share with you how to fix Unikey errors that disappear by themselves, not found.

Unikey is the most popular Vietnamese typing tool in Vietnam because they are very compact and easy to use on computers. However, many people encounter Unikey errors that automatically disappear, do not start with Windows, and do not know where to find them. In this article, Software Tips will share to you how to fix Unikey errors that disappear by themselves, not found.



## 1. Unofficial use of Unikey

Currently, there are many websites on the web reposting Unikey tool illegally, not the owner. Because of that, Unikey tools downloaded from unofficial sources often get errors and sometimes even bring Virus to your computer. To download Unikey, please visit the following website:

Unikey homepage: <https://www.unikey.org/>

## 2. Unikey "breaking" virus




Viruses are one of the common problems on computers and they often cause miscellaneous damage to the Windows operating system and software. Please run a virus scan on your computer and reinstall Unikey to see if they still encounter errors such as disappearing or not. If the error persists, please try the following methods.

### 3. Set up Unikey to start with Windows

By default, when you install Unikey, the system will not activate the feature to start with Windows, so please activate it manually.


First, you open the tool **Unikey** and find the item **Expand (1)** . Then you tick 02 items: **Enable this dialog when booting / Starting with Windows** .




### 4. Activate Unikey on the Taskbar

Not all applications appear on the Windows Taskbar, only system tools and a few specified tools are present.

**Step 1:** You proceed to press **Windows + I** to open **Settings** on the computer. Then, you enter the keyword "Select which icons appear on the taskbar" to open Taskbar settings.



**Step 2:** Then, you drag down to activate " On " for the Unikey Program is finished.




So you have completed the change, from now on Unikey will always appear on your Taskbar.




## 5. Add Unikey to boot with Windows

Adding Unikey to Windows startup files will be the most effective way to avoid them from disappearing.


**Step 1:** You proceed to open **MenuStart** and Right-click **Unikey** -> **More** -> **Open file location** .




**Step 2:** After that, right-click on the **Unikey** icon to select **Copy** .




**Step 3:** You press **Windows + R** to open the **Run** window , next enter " **shell: startup** " and click **OK** to open.




**Step 4:** After that, you proceed to **press Ctrl + V** to Paste the copied Unikey into the Startup folder.



**Step 5:** After the Unikey file is completed, right-click on the **Taskbar** to select **Task Manager**.



**Step 6:** Here, select the **Startup** tab (1) and Right-click the **Unikey Program** (2) to select **Enable** (3) .



In this article, the Software Tips guide you how to fix the error that Unikey disappears on Windows itself. Good luck!

You finished reading the article "**How to fix the error Unikey disappears itself**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.