

How to fix Windows Explorer shows the drive twice

How can I fix Windows Explorer to display 1 drive twice in the list of drives on the device?


Windows Explorer is an important part of the system. However, this tool sometimes happens to cause users to experience difficulties during use, such as a crashed Windows Explorer error. In addition, many users also reflect the status of displaying 2 identical disks on Windows Explorer.

When we connect a USB drive or an external hard drive to a computer, Windows will default to a separate drive on Windows Explorer. However, this error will display two identical drives on the list of Windows Explorer. So how to fix the error of displaying 2 identical drives on Windows Explorer?

1. How to fix Windows Explorer error has stop working?
2. Fix Windows Explorer crash on Windows 10
3. Fix Windows error without image, Thumbnail thumbnail

How to fix the current drive error twice on Windows Explorer


The current drive error twice in Windows Explorer will look like the following:



We will proceed to edit in Registry Editor to fix this problem.

Step 1:


First, press the Windows + R key combination to display the **Run dialog box** . Then enter the **keyword regedit** and click OK.



Step 2:

Switch to the Registry Editor interface. Here, go to the key below.


Computer\HKEY_LOCAL_MACHINE\SOFTWARE\Microsoft\Windows\CurrentVersion\Explorer\Desktop\NameSpace\DelegateFolders\{F5FB2C77-0E2F-4A16-A381-3E560C68BC83}



Step 3:

Then right-click on the key and **select Delete** in the list.

Shortly after returning to Windows Explorer, we will not see two drives appear.




However, this method only works with Windows 32-bit. If you use **64-bit Win**, you need to perform additional deletion, to hide the duplicate drives in the Browse and Open window, which appears when you upload photos or data to the website.

We search for the key following the path below.

Computer\HKEY_LOCAL_MACHINE\SOFTWARE\WOW6432Node\Microsoft\Windows\CurrentVersion\Explorer\Desktop\NameSpace\DelegateFolders\{F5FB2C77-0E2F-4A16-A381-3E560C68BC83}

Then the user also right click on the key and **press Delete** to delete the key.



So we have fixed the error of displaying the drive twice on the list of Windows Explorer. With the 32-bit version of Win, you only need to delete the key once. But with 64-bit Win version, it is necessary to perform one more delete of the key in order to not display the drive twice when opening Open interface, Browse.

See more:

1. Fixed a bug when Libraries folder opened automatically when booting the computer
2. How to fix the error Search Windows 10 does not work
3. 6 simple ways to open Task Manager on Windows

I wish you all success!

You finished reading the article "**How to fix Windows Explorer shows the drive twice**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.
