

How to remove default apps on Windows 10


When we install Windows 10, we will be 'attached' to a bunch of unnecessary applications. This article will guide you to remove unnecessary default applications on Win 10.

1. Uninstall default apps on Windows 10 manually

Manually uninstalling default apps is quick and simple, but sometimes they fail to remove certain applications.

Step 1: Open the **Start Menu** and search for default Windows applications that you want to delete.


Step 2: Then, **right-click** on that application and choose **Uninstall** to remove.




2. Uninstall Windows 10 default apps in Settings

Settings provides you with a wide range of settings related to the Windows 10 operating system and that includes application removal.


Step 1: You proceed to open the **Start Menu** and enter **Settings** .



Step 2: Then, you select the **Apps** tab to see all the applications installed on the computer.




Step 3: Go to the default applications of Windows 10 and choose **Uninstall** to remove them from your computer.



3. Uninstall Windows 10 default apps using PowerShell

PowerShell is a high-end code program in Windows 10, and they have access and intervention very deeply into your computer. To remove the default application using PowerShell, do the following:

Step 1: You proceed to open the Start Menu, enter **Windows PowerShell** and select **Run as Administrator** to open.



Step 2: Then, you enter 01 or all of the following commands (depending on needs) to remove the default applications.

The command to remove Movies & TV:

```
Get-AppxPackage * zunevideo * | Remove-AppxPackage
```

News removal command:

```
Get-AppxPackage * bingnews * | Remove-AppxPackage
```

OneNote removal command:

```
Get-AppxPackage * onenote * | Remove-AppxPackage
```

The People command:

```
Get-AppxPackage * people * | Remove-AppxPackage
```

Phone Companion removal command:

```
Get-AppxPackage * windowsphone * | Remove-AppxPackage
```

The command to remove Photos:

```
Get-AppxPackage * photos * | Remove-AppxPackage
```

Store removal command:

```
Get-AppxPackage * windowsstore * | Remove-AppxPackage
```

The Sport remove command:

```
Get-AppxPackage * bingsports * | Remove-AppxPackage
```

Command to remove Voice Recorder:

Get-AppxPackage * soundrecorder * | Remove-AppxPackage

The Weather command:

Get-AppxPackage * bingweather * | Remove-AppxPackage

Xbox uninstall command:

Get-AppxPackage * xboxapp * | Remove-AppxPackage

3D Builder uninstall command:

Get-AppxPackage * 3dbuilder * | Remove-AppxPackage

Alarms and Clock removal command:

Get-AppxPackage * windowsalarms * | Remove-AppxPackage

The Calculator debug statement:

Get-AppxPackage * windowscalculator * | Remove-AppxPackage

The command to remove Calendar and Mail:

Get-AppxPackage * windowscommunicationsapps * | Remove-AppxPackage

Camera removal command:

Get-AppxPackage * windowscamera * | Remove-AppxPackage

Get Office removal command:

Get-AppxPackage * officehub * | Remove-AppxPackage

Get Skype uninstall command:

Get-AppxPackage * skypeapp * | Remove-AppxPackage

Get Started statement:

Get-AppxPackage * getstarted * | Remove-AppxPackage

Groove Music removal command:

Get-AppxPackage * zunemusic * | Remove-AppxPackage

Maps removal command:

Get-AppxPackage * windowsmaps * | Remove-AppxPackage


Microsoft Solitaire Collection removal command:

Get-AppxPackage * solitairecollection * | Remove-AppxPackage

Money removal command:

Get-AppxPackage * bingfinance * | Remove-AppxPackage

Get-AppxPackage * windowscalculator * | Remove-AppxPackage



```
Administrator: Windows PowerShell
Windows PowerShell
Copyright (C) Microsoft Corporation. All rights reserved.

Try the new cross-platform PowerShell https://aka.ms/pscore6

PS C:\Windows\system32> Get-AppxPackage *zunevideo* | Remove-AppxPackage
```


4. Remove default apps on Windows 10 using the software

The current application uninstallers have been added with the default uninstall feature on Windows 10 and Iobit Uninstaller is a typical example.


Step 1: You proceed to the home page to download and install the software.

Download Iobit Uninstaller [here](#)

Step 2: At the main interface of the software, you select the **Windows Apps** tab to see all the default apps on Windows 10.



Step 3: Then, you tick the applications you want to delete (1) and click **Uninstall** (2) to delete them.



In this article, TipsMake instructed you how to uninstall all default applications on Windows 10. Have a nice day!

You finished reading the article "**How to remove default apps on Windows 10**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.