

How to restore Chrome, Firefox, IE browser to the default state?

After a long time of use, Google Chrome, Firefox or Internet Explorer web browsers fall into a slow, sluggish state. Even cleaning up each browser but the situation is not improving. The best way you should recover ...

If you use web browsers such as Google Chrome, Firefox or Internet Explorer for a long time and fall into a slow startup situation, or the operation is not as smooth as before is completely understandable. Many people choose to clean up the system, completely erase browsing history. However, the situation did not become much better.

1. **44 shortcuts are useful on all browsers**
2. **Fix IDM error without downloading download link**
3. **Top best free download support tools available today**


So do you know **the reset feature (Reset) default settings** in each browser? With a long-term use of the browser leading to sluggishness, the best way to fix that state is to restore the default settings. Follow the steps provided by the Network Administrator to bring **Google Chrome, Firefox or Internet Explorer to their original default state as they were installed.**

1. Restore default settings on Google Chrome:

Note , after reinstalling, everything opened on the browser will be deleted completely

Step 1:


In the browser Chrome, click on **the icon of the 3 dashes** on the top right and select **Settings** (Settings).



Steps to reset Chrome


Step 2:

The Settings interface appears, drag down to the bottom and select **Show advanced settings** (**Show advanced settings**) to display the **advanced settings** .




Step 3:

Scroll down and in Reset Settings (Reset Settings), click the Reset Settings button.



Step 4:

Immediately after that, a message of **Reset settings** will appear. Read the **Reset** button (Reset) to restore Google Chrome browser.



Reset Chrome by default

There is also another way to reset Chrome, which is to access the link below and click the **Reset** button to restore.

chrome: // settings / resetProfileSettings




As such, we have completed the browser restoration process. When the Reset button is clicked, the pre-set settings such as the search engine, the home page, and the new tab will return to their original state as when they were reinstalled. Your previous browsing history, Cookies, junk files, temp files, utilities, etc. were also deleted from the browser.

2. Restore Firefox browser defaults:

Firefox is also provided with the Reset browser feature.

Step 1:


Open Firefox browser. At the main interface, click on **the 3 dashes icon** in the top right corner of the screen. Then click **the question mark icon** in the bottom corner.



Reset Firefox

Step 2:

The **Help** window appears. Click **the** Troubleshooting Information section.




Step 3:

At the **Troubleshooting Information** interface, there are two options for users to choose:


1. **Refresh Firefox** : reinstall the browser to its original state, all browsing history, bookmarks, . will be erased from the browser.
2. **Safe mode** : only reboots and wipes the utilities while history, web browsing, etc. are retained.

If you want to overcome the sluggish situation, you should choose to Refresh the entire web browser.




Step 4:

A bulletin board listing the components will be removed from the browser. Click **Refresh Firefox** to reset the default settings.



Step 5:


Wait for the browser restoration process, click **Finish** (Finish) to finish.



Steps to reset Firefox

Step 6:

The data of Firefox will be saved in the computer. If necessary, you can open the folder and use it.




3. Restore Internet Explorer browser:

Although the number of Internet Explorer users is no longer as large as before, its age compared to Chrome and Firefox is much larger and is also provided with Reset features.


Step 1:

Open Internet Explorer. At the main interface, click **the gear icon** and select **Internet Opstions** .



Step 2:


The interface of Internet Options window appears. Click the **Advanced** tab and select **Reset** below.



If a prompt appears, only enable this feature without opening any browser tabs and in the unused state, you can ignore it.


Step 3:

It appears that the message lists the components that will be deleted when Internet Options resumes, including the saved password. Click **Reset** to reset the default settings.



Step 4:

After completing the recovery process, a notice board will appear. Click **Close** to complete.



Internet Options will ask you to restart the browser. Click **OK** to use.



Thus, with the above tutorial, you can completely restore the default settings for 3 popular browsers today. The method is quite simple that can overcome the sluggishness when surfing the web on browsers.

Refer to the following articles:

1. Want to browse the Web quickly, don't be foolish to clear the browser cache

1. How to remove Add-ons (Extensions) on Chrome, Firefox and some other browsers

1. Instructions to block pop-up ads in all browsers

I wish you all success!

You finished reading the article "**How to restore Chrome, Firefox, IE browser to the default state?**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.