

How to set a static IP on Windows 11 simply

Do you want to change the static IP address on Windows 11, set a static IP for your Win 11 to share the folder with other LAN users, or avoid the same IP that you can't access the network but don't know how? Let's join Taimienphi to set a static IP on Windows 11 through the following article.


Microsoft developers have changed some features and operating mechanisms, so setting **up a static IP on Windows 11** is also different from previous Win versions, so users who are not tech-savvy will not be able to do it. , and for better understanding, we will guide you **to assign static IP on Windows 11** with the most detailed illustration.




Assign IP on Windows 11 operating system

The fastest guide to setting static IP on Windows 11


Step 1: **Right** -click the **Ethernet** or **WI-Fi** icon on Windows 11 in the bottom right corner of the screen => select **Network and internet settings** .




Step 2: At the **Network & internet** panel, select **Properties** under the **Ethernet** or **WI-Fi** icon (depending on the state you are connecting to the network).



Step 3: In the new attribute table that appears, click **Edit** of the **IP assignment** entry .



Step 4: Switch from **Automatic (DHCP)** to **Manual** and **IPv4** to **On** .




Step 5: Set up the specific data boxes as follows:

- **IP Address:** Enter the static IP address **192.168.1.X** (where X is any number from 1 to 250 in the provided Wifi range, this number cannot be used). duplicate with another machine because if someone already uses this number, you won't be able to access the network)


+ For example: as shown below Taimienphi set the static IP address as **192.168.1.145**

- **Subnet mask:** Enter 255.255 .255.0


- **Gateway:** 192.168.1.1



- Preferred DNS: 8.8.8.8
 - Alternate DNS: 8.8.8.8 or 8.8.4.4
- => Click **Save** to save information.



- After setting up a static IP on Windows 11, all information will be displayed as follows



<https://thuthuat.taimienphi.vn/cach-dat-ip-tinh-tren-windows-11-68503n.aspx>

Through this article, hopefully readers know how to set static IP for Windows 11 computers. Static IP usually more stable than dynamic IP. However, because users pay little attention, we often use the default one (dynamic IP). If you have any questions during the process, feel free to ask in the comments section below.

Reference: 7 Ways to speed up Windows 11 to run faster

You finished reading the article "**How to set a static IP on Windows 11 simply**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.