

How to uninstall AMD Catalyst driver on Windows


This article provides instructions on how to uninstall the AMD Catalyst driver from Microsoft Windows-based PC systems with AMD Radeon graphics cards.

This article provides instructions on how to uninstall the AMD Catalyst driver from Microsoft Windows-based PC systems with AMD Radeon graphics cards.

NOTE : The instructions below do not apply to AMD Catalyst drivers on AMD APU systems. Systems with AMD APUs do not need to go through the driver uninstallation process before updating. To update the graphics driver on AMD APU systems, simply download and install the latest compatible AMD Catalyst driver.

How to uninstall AMD Catalyst driver on Windows 8.1 and Windows 10

1. Move the cursor to the lower left of the desktop or the Metro user interface. The **Start** box will immediately appear.
2. Right-click on the screen to open the context menu and select **Control Panel**.



Open Control Panel

3. Select **Programs and Features** in **Control Panel** and follow the steps mentioned in *Uninstalling AMD Catalyst Install Manager (CIM) from Control Panel* .

How to uninstall AMD Catalyst driver on Windows Vista and Windows 7

1. Click **Start**.


2. Open Control Panel.

3. Select **Programs and Features** from **Control Panel** and follow the steps mentioned in the section of *Uninstalling AMD Catalyst Install Manager (CIM) from Control Panel* .

Uninstall AMD Catalyst Install Manager (CIM) from Control Panel

1. In **Control Panel** , select **AMD Catalyst Install Manager** .

2. Click **Change**.



Click on **Change**

3. When prompted by AMD Catalyst Install Manager - InstallShield Wizard, click **Next**.


4. When prompted by the AMD Catalyst Install Manger - InstallShield Wizard, select **Express Uninstall ALL AMD Software** .

NOTE : Windows User Account Control (UAC) may ask '**Do you want to allow the following program from an unknown publisher to make changes to this computer?**' (*Do you want to allow the following program*

from an unknown manufacturer to make changes to this computer?) . If that happens, click **Yes** to continue the uninstall process.

5. Click **All Versions** to allow AMD Catalyst Install Manager to remove all previous versions of AMD drivers and AMD application components installed by CIM.

Clicking **Current Version** will only uninstall the latest version of drivers and components.



Click All Versions to allow AMD Catalyst Install Manager to delete all previous versions of AMD drivers
6. The uninstall process will begin.

7. When prompted to uninstall AMD Catalyst Install Manager, click **Remove**.

8. Click **Finish**.

9. Click **Yes** when prompted to restart the system and complete the uninstall process.

To verify that the AMD Catalyst driver and all related software has been removed from the system, return to the **Program and Features list** and check to see if any AMD entries are found. If there are specific AMD entries still listed, delete them using the above procedure.


How to uninstall AMD Catalyst driver on Windows XP / Windows 2000

1. Click on **Start**.

2. Open **Control Panel**.

3. Select **Add or Remove Programs**.

4. From the list of currently installed programs, select **AMD Catalyst Install Manager** .



Select AMD Catalyst Install Manager

5. Select **Change** and continue with the uninstall steps.

6. Reboot the system.

You finished reading the article "**How to uninstall AMD Catalyst driver on Windows**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.