


How to update driver on Windows 10, 11

During the process of using the computer, sometimes the driver is faulty and you want to update the driver to a newer one. Below is the current easy way to update drivers on Windows 10, 11.


During the process of using the computer, sometimes your driver is faulty or you want to update a newer driver. But you do not know how to update the driver? In this article, TipsMake.com shares with you how to update drivers on Windows 10, 11 quickly and effectively, please refer to it.




1. How to update driver via Device Manager

Updating drivers via Device Manager is a quick way to update drivers on Windows 10, 11, you do the following:


Step 1 : On Windows 10, 11 computer, right-click on the **Start** menu and select **Device Manager** .



Step 2 : On **Device Manager** , find and expand the driver section you want to update (**Display adapters** for graphics card, **Sound, video and game controllers** for sound,.)




Step 3 : Right-click on the driver you want to update and select **Update driver** .




Step 4 : 2 options appear, choose the appropriate option to update the driver

1. **Search automatically** for updated driver software: Select this option, Windows will automatically find and install the latest driver if available.
2. **Browse my computer** for driver software: Select this option if you downloaded the driver from the manufacturer's website and want to install the driver manually.




Step 5 : After the driver update process is complete, restart your computer to apply the changes.




2. How to update driver via Windows Update

Updating Windows is also a quick and simple way to update drivers on Windows 10, 11. You do the following:


Step 1 : Press Windows + I to open the Settings window , then select **Windows Update** (or **Update & Security** ? **Windows Update** with Windows 10).



Step 2 : Click **Check for updates** , Windows will search for updates including driver updates.



Step 3 : Windows will automatically download and install drivers into the system.




Step 4 : After updating the driver on Windows 10, 11, you need to restart the computer to update the changes.


3. How to update driver using manufacturer's website

Searching and downloading drivers on the manufacturer's website is also an effective way to manually update drivers on Windows 10, 11. You can do the following:

Step 1 : Go to the hardware manufacturer's website (e.g. Realtek, NVIDIA, Intel, AMD) and find the latest driver for your device to download.



Step 2 : Run the installation file and install the driver on your computer. After installation is complete, restart your computer for the new driver to be applied.



Above, TipsMake.com has shared with you simple and quick ways to update drivers on Windows 10, 11. Hopefully after reading this article, you can easily update drivers to the latest version to experience your computer in the best and most convenient way. Thank you for your interest and following this article.

You finished reading the article "**How to update driver on Windows 10, 11**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.