

Instructions from A-Z how to remove advertising programs on Windows computers

Pop-Up Ads (pop up ads) created by Adware or ad-supported software that automatically renders ads on victim's computer to make money from those ads. Although advertising is a legitimate solution for advertisers to promote their products (such as on Internet sites), software designed for that job, often referred to as promo software fox.

Pop-Up Ads (pop up ads) created by Adware or ad-supported software that automatically renders ads on victim's computer to make money from those ads. Although advertising is a legitimate solution for advertisers to promote their products (such as on Internet sites), software designed for that job, often called "Software advertisement". In most cases, however, Malware and 'produced' ads from the software are displayed on the user's computer in the form of a pop-up window (pop-up). advertisement).

Technically Adware (adware) is not a virus that is classified as a malware program (unwanted program (PUP) can contain and install malicious programs on your computer, like adware, toolbars or viruses. If a computer is 'victim' of Adware (adware), then there will be lots of popup ads, banner and sponsored link (Sponsored links are displayed on the screen or inside the Internet browser, and in some cases, computer speed may be 'slow' due to malicious programs running in the background.

Program, adware (Adware) can be installed without the user's notice. This is because Adware (adware) is often 'packaged' within other free software that users download and install from unknown sites .

So when you install any program or software you need to pay attention to the program installation options, because most software installers contain additional software that you never want to install. put on your computer.

When installing any program on your computer, you need to pay attention:

1. On the installation screen, do not click the Next 'button too fast'.
2. Read carefully and accept the terms carefully.
3. Always select the 'Custom' setting.
4. Reject settings that require additional software that you do not want to install.
5. Uncheck any options saying that the homepage and search settings will be changed.


Remove ads and adware on computers

Step 1: Uninstall Adware on Control Panel

1. To do this:

- On Windows 8/7 / Vista: Access **Start => Control Panel** .


- On Windows XP: Go to **Start => Settings => Control Panel** .



2. On the Control Panel window:


- Find and double-click **Add or Remove Programs** if you use Windows XP.

- Find and double-click **Programs and Features** if you use Windows 8, 7 or Vista.



3. At this time, the screen shows the list of programs installed on the system. Here you click **Install On** to arrange the installation program by day, then find and uninstall unknown programs or programs installed on the latest system. Also find and remove the following programs:

1. Media Player
2. SaveSense
3. SavingsBull or SavingsBullFilter
4. Scorpion Saver
5. TheBlocker
6. VideoPlayer
7. YouTubeAdBlocker



Step 2: Remove unwanted Toolbar Adware and Toolbar from your browser


AdwCleaner is a free tool to remove adware, unwanted programs (PUP), Toolbar and browser attacker (Hijacker) on your computer easily.

1. Download AdwCleaner to your device and install it.

Download AdwCleaner to your device and install it here.

2. Close all open programs on your computer, then double click to open AdwCleaner.

3. After accepting the terms, click the **Scan** button .



4. Wait until the scan has finished, click **Clean** to remove all unwanted malware on your system.



5. On the AdwCleaner - Information window, click **OK** , then select **OK** again to restart your computer.




6. When your computer is restarted, close the AdwCleaner "window" and proceed to the next step.

Step 3: Remove unwanted programs with Junkware Removal Tool


1. Download the Junkware Removal Tool on your device and run the tool.

Download the Junkware Removal Tool on your device and install it here.


2. Press any key to start scanning your computer using the JRT - Junkware Removal Tool.



3. Wait until the JRT - Junkware Removal Tool scans and "cleans" your system.




4. Close the JRT window and restart your computer.




Step 4: Remove Ads and Adware extensions from IE, Google Chrome and Firefox browsers

- On Internet Explorer:


1. In Internet Explorer, click the jagged icon in the top right corner to open the browser menu, then click **Tools** => **Internet Options** .



2. In the Internet Options window, click the **Advanced tab** .




3. Select **Reset** .



4. Check the Delete personal settings option and click Reset.




5. After the reset process finishes, click **Close** and select **OK** to exit the Internet Explorer options window.




6. Close all windows and restart Internet Explorer.

- Google Chrome browser:


1. Open the Chrome browser on your computer, then click the 3 dash icon in the top right corner of the screen, select **Settings** .



2. On the Settings window, find and click the option Show advanced settings (show advanced settings).



3. Scroll down to find and select **Reset Browser Settings** button.




4. In the Reset browser settings dialog window, click **Reset** .




5. Restart your Chrome browser.

- Mozilla Firefox browser:

1. On the Firefox Menu, access **Help => Troubleshooting information** .



2. Next on the Troubleshooting Information window, click the button Reset Firefox to reset Firefox browser to its default state.



3. Click Reset Firefox again.



4. After the reset process finishes, restart your Firefox browser.

Step 5: Clean up the remaining malicious files on your computer

Download Malwarebytes Anti-Malware Premium to your device and install it.

Download Malwarebytes Anti-Malware Premium to your computer and install it here.

- Download and install Malwarebytes Anti-Malware Premium:


1. After downloading Malwarebytes Anti-Malware Premium, run the file.
1. To install and use the free program, uncheck the Enable free Trial of Malwarebytes Anti-Malware Premium section on the final installation window.

- Scan and clean your computer with Malwarebytes Anti-Malware:


1. Run Malwarebytes Anti-Malware and allow the program to update (update) the latest version (if needed).




2. After the update process finishes, click the **Scan Now** button to start the scan of your system, remove malware and unwanted programs.




3. Wait until the end of the system scan.



4. Click the Quarantine All button to remove all "threats" found on your system.



5. After the process has finished, restart your computer to complete the process.



6. After the computer has finished booting, run Malwarebytes' Anti-Malware again to confirm there are no "threats" on your system.

Step 6: Clean up unwanted files and items on the system

Use the CCleaner program and take steps to clean the system from temporary Internet files and registry error entries.

1. Download CCleaner and install it here.

Refer to some of the following articles:

1. How to set up Private Network on Windows 10?
1. Remove root malware (malware) on Windows 10 computers
1. Rooted Delta Search on Chrome, Firefox and Explorer browsers

Good luck!

You finished reading the article "**Instructions from A-Z how to remove advertising programs on Windows computers**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.