

Instructions to disable Microsoft Consumer Experiences on Windows 10

On Windows 10 system, Microsoft installs or proposes to install applications, Windows games Store like Candy Crush Soda Saga, Flipboard, Twitter, Photoshop Express, Minecraft To be able to do this, Microsoft uses Use Microsoft Consumer Experiences features built into Windows 10.


On Windows 10 system, Microsoft installs or proposes to install applications, Windows games Store like Candy Crush Soda Saga, Flipboard, Twitter, Photoshop Express, Minecraft . To be able to do this, Microsoft uses Use Microsoft Consumer Experiences features built into Windows 10.

However every time you uninstall these applications, Microsoft will re-suggest, display the installation of other applications. If you don't want to, or if you find it annoying, you can disable Microsoft Consumer Experiences on Windows 10.

Turn off Microsoft Consumer Experiences

To turn off Microsoft Consumer Experiences feature, you can use the Group Policy Editor or the Registry Editor.

1. Turn off Microsoft Consumer Experiences with Group Policy Editor



Press **Windows + X** key combination to open the Power user Menu, then click **Run** to open the Run command window.

On the Run command window, type **gpedit.msc** and press Enter to open the Group Policy Editor.

On the Group Policy Editor window you navigate to the key:

Computer Configuration> Administrative Templates> Windows Components> Cloud Content

Next, double-click the **Turn off Microsoft consumer experience option** to open the Turn off Microsoft consumer experience Properties window.

Here you click **Enabled** and then click **Apply** .

From now on, Microsoft Consumer Experiences features are disabled on Windows 10.

2. Use Registry Editor

If your version of Windows 10 does not support Group Policy Editor, you can use the Registry Editor to disable Microsoft Consumer Experiences.

First open the Run dialog box, then enter the **regedit** command there to open the Registry Editor. In the Registry Editor window, navigate to the key:

HKEY_LOCAL_MACHINESOFTWAREPoliciesMicrosoftWindowsCloudContent

Next, find and double-click the **DisableWindowsConsumerFeatures** option in the right pane and then change the DWORD value to **1**.

If DWORD does not exist, you can create a new DWORD.

From now on the Microsoft Consumer Experience feature on Windows 10 has been disabled.

Refer to some of the following articles:

1. Steps to restore Windows Store on Windows 10 after removal
1. How to fix the screen error of Windows 7/8 / 8.1 / 10 is black
1. Fix Windows 10 error with just one click with FixWin

Good luck!

You finished reading the article "**Instructions to disable Microsoft Consumer Experiences on Windows 10**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.