

Trick to increase the number of items displayed in Jump List on Windows 10

Normally, Jump List only displays 12 items but if you want to increase more, you have to perform tricks to change the number of items displayed in Jump List on Windows 10, here are tips to increase the number of items in Jump List.

See also: [Steps to clear Jump Lists history on Windows 10](#)

[Access commonly used items in Windows 7 with Jump Lists](#)


In previous versions of Windows, users could change the number of recently visited folders displayed in the Jump List with a simple option in the taskbar. However, Microsoft removed this feature in Windows 10 version without giving any reason. But okay, just a few small tricks you can increase the number of items in the Jump List.

Increase the Jump List limit by editing Registry Manually

By default Windows 10 only displays 12 items in the Jump List. To increase the number of items, you only need to change the settings in the Windows Registry.


Note: Registry Editor is a powerful tool. If you misuse it, your computer may become unstable or even shut down. This is a pretty simple trick, if you follow the instructions, there won't be any problems. If you haven't used the Registry, read the instructions before starting. Make sure you back up the Register (and the computer) before making changes.

Open Register Editor by clicking on Start and typing "**regedit**". Press Enter to open Register Editor and allow changes to your computer.




In the **Register Editor** window, use the left bar to follow these instructions:


HKEY_CURRENT_USERSOFTWAREMicrosoftWindowsCurrentVersionExplorerAdvanced



Next, create and name the new value domain inside **Advanced** key . Right-click on the **Advanced** folder and select **New> DWORD (32-bit) Value** . Name the new value **JumpListItems_Maximum** , then double-click the value to open its properties window.



In the properties window of the value, enter the number of new entries that you want the jump list to display in **the "Value data" box** . Numbers ranging from 15 to 20 are quite reasonable numbers and still allow all Jump Lists to display on the screens. However, you can set a higher number if you want, then click OK.



You can now exit Registry Editor without restarting the computer or doing anything else. The change will take effect immediately so just open a jump list to check if you have finished. In the tutorial, we have increased the number to 20 and you can see that many other items are displayed.

Recent

 File 1.docx

 File 2.docx

 File 3.docx

 File 4.docx

 File 5.docx

 File 6.docx

 File 7.docx

 File 8.docx

 File 9.docx

 File 10.docx

 File 11.docx

 File 12.docx

 File 13.docx

 File 14.docx

 File 15.docx

 File 16.docx

 File 18.docx

 File 19.docx

 File 20.docx

If you want to reset the default number of items, just return to Advanced key and set the **JumpListItems_Maximum** value to 0.

When you increase the item displayed in Jump List, users will also be able to easily open multiple folders, files or web pages faster without having to open them through support tools and software.

You finished reading the article "**Trick to increase the number of items displayed in Jump List on Windows 10**" edited by the [TipsMake](#) team. We hope this article has provided you with many useful tech tips and tricks. You can search for similar articles on tips and guides. Thank you for reading and for following us regularly.